

NAME

pod2man - Convert POD data to formatted *roff input

SYNOPSIS

```
pod2man [--center=string] [--date=string] [--fixed=font] [--fixedbold=font] [--fixeditalic=font] [
--fixedbolditalic=font] [--name=name] [--official] [--quotes=quotes] [--release[=version]] [--section=
manextf] [--stderr] [--utf8] [--verbose] [input [output] ...]
```

pod2man --help

DESCRIPTION

pod2man is a front-end for Pod::Man, using it to generate *roff input from POD source. The resulting *roff code is suitable for display on a terminal using nroff(1), normally via man(1), or printing using troff(1).

input is the file to read for POD source (the POD can be embedded in code). If *input* isn't given, it defaults to STDIN. *output*, if given, is the file to which to write the formatted output. If *output* isn't given, the formatted output is written to STDOUT. Several POD files can be processed in the same **pod2man** invocation (saving module load and compile times) by providing multiple pairs of *input* and *output* files on the command line.

--section, **--release**, **--center**, **--date**, and **--official** can be used to set the headers and footers to use; if not given, Pod::Man will assume various defaults. See below or *Pod::Man* for details.

pod2man assumes that your *roff formatters have a fixed-width font named `cw`. If yours is called something else (like `CR`), use **--fixed** to specify it. This generally only matters for troff output for printing. Similarly, you can set the fonts used for bold, italic, and bold italic fixed-width output.

Besides the obvious pod conversions, Pod::Man, and therefore pod2man also takes care of formatting `func()`, `func(n)`, and simple variable references like `$foo` or `@bar` so you don't have to use code escapes for them; complex expressions like `$fred{'stuff'}` will still need to be escaped, though. It also translates dashes that aren't used as hyphens into en dashes, makes long dashes--like this--into proper em dashes, fixes "paired quotes," and takes care of several other troff-specific tweaks. See *Pod::Man* for complete information.

OPTIONS

-c *string*, **--center**=*string*

Sets the centered page header to *string*. The default is "User Contributed Perl Documentation", but also see **--official** below.

-d *string*, **--date**=*string*

Set the left-hand footer string to this value. By default, the modification date of the input file will be used, or the current date if input comes from STDIN.

--fixed=*font*

The fixed-width font to use for verbatim text and code. Defaults to `cw`. Some systems may want `CR` instead. Only matters for troff(1) output.

--fixedbold=*font*

Bold version of the fixed-width font. Defaults to `CB`. Only matters for troff(1) output.

--fixeditalic=*font*

Italic version of the fixed-width font (actually, something of a misnomer, since most fixed-width fonts only have an oblique version, not an italic version). Defaults to `CI`. Only matters for troff(1) output.

--fixedbolditalic=*font*

Bold italic (probably actually oblique) version of the fixed-width font. Pod::Man doesn't assume you have this, and defaults to `CB`. Some systems (such as Solaris) have this font available as `CX`. Only matters for troff(1) output.

-h, --help

Print out usage information.

-l, --lax

No longer used. **pod2man** used to check its input for validity as a manual page, but this should now be done by *podchecker(1)* instead. Accepted for backward compatibility; this option no longer does anything.

-n name, --name=name

Set the name of the manual page to *name*. Without this option, the manual name is set to the uppercased base name of the file being converted unless the manual section is 3, in which case the path is parsed to see if it is a Perl module path. If it is, a path like `.../lib/Pod/Man.pm` is converted into a name like `Pod::Man`. This option, if given, overrides any automatic determination of the name.

Note that this option is probably not useful when converting multiple POD files at once. The convention for Unix man pages for commands is for the man page title to be in all-uppercase even if the command isn't.

-o, --official

Set the default header to indicate that this page is part of the standard Perl release, if **--center** is not also given.

-q quotes, --quotes=quotes

Sets the quote marks used to surround `C<>` text to *quotes*. If *quotes* is a single character, it is used as both the left and right quote; if *quotes* is two characters, the first character is used as the left quote and the second as the right quoted; and if *quotes* is four characters, the first two are used as the left quote and the second two as the right quote.

quotes may also be set to the special value `none`, in which case no quote marks are added around `C<>` text (but the font is still changed for troff output).

-r, --release

Set the centered footer. By default, this is the version of Perl you run **pod2man** under. Note that some system an macro sets assume that the centered footer will be a modification date and will prepend something like "Last modified: "; if this is the case, you may want to set **--release** to the last modified date and **--date** to the version number.

-s, --section

Set the section for the `.TH` macro. The standard section numbering convention is to use 1 for user commands, 2 for system calls, 3 for functions, 4 for devices, 5 for file formats, 6 for games, 7 for miscellaneous information, and 8 for administrator commands. There is a lot of variation here, however; some systems (like Solaris) use 4 for file formats, 5 for miscellaneous information, and 7 for devices. Still others use 1m instead of 8, or some mix of both. About the only section numbers that are reliably consistent are 1, 2, and 3.

By default, section 1 will be used unless the file ends in `.pm`, in which case section 3 will be selected.

--stderr

By default, **pod2man** puts any errors detected in the POD input in a POD ERRORS section in the output manual page. If **--stderr** is given, errors are sent to standard error instead and the POD ERRORS section is suppressed.

-u, --utf8

By default, **pod2man** produces the most conservative possible **roff* output to try to ensure that it will work with as many different **roff* implementations as possible. Many **roff* implementations cannot handle non-ASCII characters, so this means all non-ASCII characters are converted either to a **roff* escape sequence that tries to create a properly accented character (at least for *troff* output) or to *x*.

This option says to instead output literal UTF-8 characters. If your **roff* implementation can handle it, this is the best output format to use and avoids corruption of documents containing non-ASCII characters. However, be warned that **roff* source with literal UTF-8 characters is not supported by many implementations and may even result in segfaults and other bad behavior.

Be aware that, when using this option, the input encoding of your POD source must be properly declared unless it is US-ASCII or Latin-1. POD input without an `=encoding` command will be assumed to be in Latin-1, and if it's actually in UTF-8, the output will be double-encoded. See *perlpod(1)* for more information on the `=encoding` command.

-v, --verbose

Print out the name of each output file as it is being generated.

DIAGNOSTICS

If **pod2man** fails with errors, see *Pod::Man* and *Pod::Simple* for information about what those errors might mean.

EXAMPLES

```
pod2man program > program.1
pod2man SomeModule.pm /usr/perl/man/man3/SomeModule.3
pod2man --section=7 note.pod > note.7
```

If you would like to print out a lot of man page continuously, you probably want to set the C and D registers to set contiguous page numbering and even/odd paging, at least on some versions of *man(7)*.

```
troff -man -rC1 -rD1 perl.1 perldata.1 perlsyn.1 ...
```

To get index entries on `STDERR`, turn on the F register, as in:

```
troff -man -rF1 perl.1
```

The indexing merely outputs messages via `.tm` for each major page, section, subsection, item, and any `x<>` directives. See *Pod::Man* for more details.

BUGS

Lots of this documentation is duplicated from *Pod::Man*.

SEE ALSO

Pod::Man, *Pod::Simple*, *man(1)*, *nroff(1)*, *perlpod(1)*, *podchecker(1)*, *perlpodstyle(1)*, *troff(1)*, *man(7)*

The man page documenting the an macro set may be *man(5)* instead of *man(7)* on your system.

The current version of this script is always available from its web site at <http://www.eyrie.org/~eagle/software/podlators/>. It is also part of the Perl core distribution as of 5.6.0.

AUTHOR

Russ Allbery <rra@stanford.edu>, based very heavily on the original **pod2man** by Larry Wall and Tom Christiansen.

COPYRIGHT AND LICENSE

Copyright 1999, 2000, 2001, 2004, 2006, 2008, 2010 Russ Allbery <rra@stanford.edu>.

This program is free software; you may redistribute it and/or modify it under the same terms as Perl itself.