



Install BA Server with Your Own BA Repository



This document supports Pentaho Business Analytics Suite 5.0 GA and Pentaho Data Integration 5.0 GA, documentation revision September 5 2013, copyright © 2013 Pentaho Corporation. No part may be reprinted without written permission from Pentaho Corporation. All trademarks are the property of their respective owners.

Help and Support Resources

If you do not find answers to your questions here, please contact your Pentaho technical support representative.

Support-related questions should be submitted through the Pentaho Customer Support Portal at <http://support.pentaho.com>.

For information about how to purchase support or enable an additional named support contact, please contact your sales representative, or send an email to sales@pentaho.com.

For information about instructor-led training, visit <http://www.pentaho.com/training>.

Liability Limits and Warranty Disclaimer

The author(s) of this document have used their best efforts in preparing the content and the programs contained in it. These efforts include the development, research, and testing of the theories and programs to determine their effectiveness. The author and publisher make no warranty of any kind, express or implied, with regard to these programs or the documentation contained in this book.

The author(s) and Pentaho shall not be liable in the event of incidental or consequential damages in connection with, or arising out of, the furnishing, performance, or use of the programs, associated instructions, and/or claims.

Trademarks

Pentaho (TM) and the Pentaho logo are registered trademarks of Pentaho Corporation. All other trademarks are the property of their respective owners. Trademarked names may appear throughout this document. Rather than list the names and entities that own the trademarks or insert a trademark symbol with each mention of the trademarked name, Pentaho states that it is using the names for editorial purposes only and to the benefit of the trademark owner, with no intention of infringing upon that trademark.

Third-Party Open Source Software

For a listing of open source software used by each Pentaho component, navigate to the folder that contains the Pentaho component. Within that folder, locate a folder named licenses. The licenses folder contains HTML files that list the names of open source software, their licenses, and required attributions.

Contact Us

Global Headquarters Pentaho Corporation
Citadel International, Suite 340
5950 Hazeltine National Drive
Orlando, FL 32822
Phone: +1 407 812-OPEN (6736)
Fax: +1 407 517-4575
<http://www.pentaho.com>

Sales Inquiries: sales@pentaho.com

Contents

Introduction.....	4
Overview of the Installation Process.....	5
Prepare Environment.....	6
Create User Account.....	6
Create Windows User Account.....	6
Create Linux User Account.....	6
Create Directory Structure.....	7
Create Windows Directory Structure.....	7
Create Linux Directory Structure.....	7
Install the BA Repository Database.....	7
Download and Unpack Installation Files.....	8
Install Java JRE or JDK.....	8
Set Environment Variables.....	9
Set Windows PENTAHO_JAVA_HOME Variable.....	9
Set Linux PENTAHO_JAVA_HOME Variable.....	9
Adjust Amount of Memory Mac OS Allocates for PostgreSQL.....	10
Initialize Repository.....	11
Initialize PostgreSQL BA Repository Database.....	11
Initialize MySQL BA Repository Database.....	13
Initialize Oracle BA Repository Database.....	13
Configure Repository.....	15
Configure PostgreSQL BA Repository Database.....	15
Configure Quartz on PostgreSQL BA Repository Database.....	15
Configure Hibernate Settings for PostgreSQL BA Repository Database.....	15
Modify Jackrabbit BA Repository Information for PostgreSQL.....	16
Prepare MySQL BA Repository Database.....	19
Configure Quartz on MySQL BA Repository Database.....	19
Configure Hibernate Settings for MySQL.....	19
Modify Jackrabbit Repository Information for MySQL.....	19
Prepare Oracle BA Repository Database.....	22
Configure Quartz on Oracle BA Repository Database.....	22
Configure Hibernate Settings for Oracle.....	22
Modify Jackrabbit Repository Information for Oracle.....	23
Specify Connections.....	27
Perform Tomcat-Specific Connection Tasks.....	27
Download and Install Repository Database JDBC Drivers.....	27
Download and Install H2 JDBC Drivers.....	27
Modify JDBC Connection Information in the Tomcat context.xml File.....	27
Start BA Server.....	30
Install BA Server License Keys.....	30
Modify Tomcat Startup Script.....	30
Modify the Tomcat Windows Startup Script.....	30
Modifying the Tomcat Linux Startup Script.....	30
Starting the BA Server.....	31
Windows Pentaho Archive Installation.....	31
Linux Pentaho Archive Installation.....	31
Next Steps.....	32

Introduction

This section explains how to install Business Analytics (BA) Server and configure it to use the BA Repository database of your choice. The BA Repository contains solution content, scheduling, and audit tables needed for the BA Server to operate. You can house the BA Repository on PostgreSQL, MySQL, or Oracle. With this installation option, you must supply, install, and configure your chosen database yourself.

Prerequisites

Read [Select BA Installation Option](#) to make sure that this is the best installation option for you. Then, check the [Supported Technologies](#) tables to make sure that your server computer, BA Repository database, and web browser meet Pentaho's requirements for this version of the software.

Expertise

The topics in this section are written for IT administrators, evaluators, and analysts who have who have access to the server on which the BA Server will be installed. You should know where data is stored, how to connect to it, details about the computing environment, and how to use the command line to issue commands for Microsoft Windows or Linux. You should also know how to install a database.


Tools

You will need a text editor and a zip tool to complete some of the steps in this installation process.

Login Credentials

All of the tasks in this section require that you have the appropriate permissions and accesses required to install software on servers and workstations.


Overview of the Installation Process



To install the BA Server, perform the tasks indicated in the *guidepost*.

- **Prepare Environment:** Explains how to prepare your computer for the installation process.
- **Initialize Repository:** Provides information about how to run DDL scripts that create tables for the BA Repository.
- **Configure Repository:** Provides information about how to configure the BA Repositories on your selected database.
- **Specify Connections:** Explains how to specify the JDBC connections to the BA Repository.
- **Start BA Server:** Explains how to start the BA Server.
- **Next Steps:** Indicates what to do after the BA Server has been installed.

Prepare Environment



To prepare the computer on which you plan to install the BA Server, complete these tasks.

- [Create a pentaho user account if you plan to install the BA Server on a Linux machine.](#)
- [Install the BA Repository database.](#) If you already have a database installed, skip this task.
- [Download and unpack the installation files.](#)
- [Install Java JRE or JDK.](#)
- [Set environment variables.](#)
- [Perform advanced preparations, if necessary.](#)

Create User Account

Create Windows User Account

If you plan to install on a server that runs Windows, you do not need to create a special user account on the server. However, you should use an account that has administrator privileges to complete the tasks in these instructions.

Create Linux User Account

If you plan to install the BA Server in a Linux environment you must create a user account named **pentaho** on the server computer. By default, license information for Pentaho products is stored in the home directory for this account. Use this account to perform installation tasks that do not require root access. Also, use this account to run start and stop server scripts.

1. Open a **Terminal** window on the server. If you plan to install the BA Server on a remote computer, establish an OpenSSH session to the remote server.
2. In the **Terminal** window, log in as the **root** user by typing this command.

```
su root
```

3. When prompted, type the password in the **Terminal** window.
4. In the **Terminal** window, create a new user account called **pentaho**, along with the `pentaho` home directory, by typing this line.

```
sudo useradd -s /bin/bash -m pentaho
```

Note: `/bin/bash` indicates that the user account should be created using the Bash shell. In many Linux distributions, the default new user shell is `/bin/sh` or some equivalent, such as Dash, that might not use the `~/ .bashrc` configuration file by default. If you don't have or want to use Bash, adjust the instructions throughout in this section accordingly.

5. In the **Terminal** window, assign a password for the **pentaho** user by typing this line.

```
sudo passwd pentaho
```

6. Verify that you can log in using the newly-created **pentaho** user account.
 - a) In the **Terminal** window, attempt to log in by typing this line.

```
su pentaho -
```

- b) Type the password for the **pentaho** user account if you are prompted.
- c) Use the **Terminal** window to navigate to the `pentaho` directory to verify that it has been created. By default, it is in the `/home` directory.

- d) Close the **Terminal** window.

Create Directory Structure

Create Windows Directory Structure

1. Log into the machine on which you will run the BA Server.
2. Create this directory path.

```
pentaho/server
```

3. Verify that you have the appropriate permissions to read, write, and execute commands in the directories you created.
 - a) Open **Windows Explorer** and right-click the `pentaho` directory.
 - b) Select the **Properties** option and the **Security** tab to verify that you have read, write, and execute permissions.
 - c) In **Windows Explorer** navigate to `server` directory, then right-click.
 - d) Select the **Properties** option and the **Security** tab to verify that you have read, write, and execute permissions.

Create Linux Directory Structure

1. Log into the machine on which you will run the BA Server. Make sure that you are logged in as the **pentaho** user.
2. Create this directory path from home directory (`pentaho`).

```
pentaho/server
```

3. Verify that you have the appropriate permissions to read, write, and execute commands in the directories you created.
 - a) In Linux check the permissions of the `pentaho`, `server`, and `biserver-ee` directories by opening a **Terminal** window, navigating to the `pentaho` directory, then typing this command.

```
ls -ld ../pentaho ../pentaho/server
```

- b) Make sure that permissions for the directories allow you to read, write, and execute in those directories.

Install the BA Repository Database

The BA Repository houses data needed for Pentaho tools to provide scheduling and security functions, as well as metadata and models for reports that you create.

You can choose to host the BA Repository on the PostgreSQL, MySQL, or Oracle database. By default, Pentaho software is configured to use the PostgreSQL Database. If you already have a BA Repository database installed, you can skip this step.

1. To download and install the BA Repository database, use the instructions in the documentation for the database of your choice. It does not matter where you install the database.
2. Verify that the BA Repository database is installed correctly. You can do this by connecting to your database and viewing the contents of any default databases that might have been created upon installation. Consult the user documentation for the database that you installed for further details.

Note: If you are not familiar with SQL, consider using a visual database design tool to connect to the database and view its contents.

- PGAdminIII is bundled with PostgreSQL.
- MySQL Workbench can be used with MySQL. It is available as a separate download. Check the MySQL site for details on how to obtain this design tool.
- Oracle SQL Developer can be used with Oracle. It is available as a separate download. Check the Oracle site for details on how to obtain this design tool.

Download and Unpack Installation Files

If you want to install specific Pentaho software, obtain the installation packages from the Pentaho Customer Support Portal. Consult your Welcome Kit if you need more information about the portal. The Pentaho BA Server software, data files, and examples are stored in pre-packaged `.war` and `.zip` files. Manually copy these files to correct directories.

1. Make sure the web application server on which you plan to deploy the BA Server has been stopped.
2. Download the `biserver-ee-5.0.0-dist.zip`.
3. Unpack the file by completing these steps.
 - a) Use a zip tool to extract the `biserver-ee-5.0.0-dist.zip` file you just downloaded.
 - b) Open a **Command Prompt** or **Terminal** window and navigate to the folder that contains the files you just extracted.
 - c) Enter one of the following at the prompt.

Windows:

```
install.bat
```

Linux:

```
./install.sh
```

- d) Read the license agreement that appears. Select **I accept the terms of this license agreement**, then click **Next**.

Note: If you are unpacking the file in a non-graphical environment, open a **Terminal** or **Command Prompt** window and type `java -jar install.jar -console` and follow the instructions presented in the window.
- e) Indicate where you want the file to be unpacked. It doesn't matter where because you will be manually placing the files in the appropriate directories later in these instructions.
- f) Click the **Next** button.
- g) The **Installation Progress** window appears. Progress bars indicate the status of the installation. When the installation progress is complete, click **Quit** to exit the Unpack Wizard.
4. Navigate to the directory where you unpacked the files. Unzip the file and extract it to the `pentaho/server` directory you created in the directory creation step.
5. Verify that the files have been placed in the following places by comparing the following directory structure with yours.

- **Tomcat File Locations:**

- `pentaho/server/biserver-ee/tomcat/webapps/pentaho.war`
- `pentaho/server/biserver-ee/tomcat/webapps/pentaho-style.war`
- `pentaho/server/biserver-ee/data`
- `pentaho/server/biserver-ee/pentaho-solutions`
- `pentaho/server/biserver-ee/pentaho-solutions/systems/default-content`

- **JBoss File Locations:**

- `pentaho/server/biserver-ee/jboss/standalone/deployments/pentaho.war`
- `pentaho/server/biserver-ee/jboss/standalone/deployments/pentaho-style.war`
- `pentaho/server/biserver-ee/data`
- `pentaho/server/biserver-ee/pentaho-solutions`
- `pentaho/server/biserver-ee/pentaho-solutions/systems/default-content`

Note: If your web application server is not in the `pentaho/server/biserver-ee` directory, the `pentaho.war` and `pentaho-style.war` files appear where you've chosen to install your web application server.

Install Java JRE or JDK

Make sure that the version of the Java Runtime Environment (JRE) or the Java Development Kit (JDK) that Pentaho needs to run is installed on your system. You do not need to uninstall other versions of Java if you already have them running on your system. These instructions explain how to check for your default version of Java that is running on your computer and where to get the required version if you need one.

1. Check the [supported technologies](#) list to see which version of the JRE or JDK is needed for the software.
2. If you have not done so already, log into the computer on which you plan to install the software. Ensure that you have the appropriate permissions to install software.
3. Open a **Terminal** or a **Command Prompt** window. Enter this command.

```
java -version
```

4. If the version of Java does not match the version needed to run Pentaho software, check your system to see if there are other versions of Java installed.
5. If the version of Java that you need to run Pentaho software is not on your system, [download it from the Oracle site](#) and install it.

Set Environment Variables

Set the `PENTAHO_JAVA_HOME` variable to indicate the path to the Java JRE or JDK that Pentaho should use. If you do not set this variable, then Pentaho will not start correctly. To set environment variables, you should be logged into an account that has administrator-level privileges. For Linux systems, you must be logged into the **root** user account.

Set Windows PENTAHO_JAVA_HOME Variable

1. From the **Start** menu, right-click **Computer**, then select **Properties**.
2. Click **Advanced System Settings**. The **System Properties** window appears.
3. In the **System Properties** window, click the **Advanced** tab, then click **Environment Variables**.
4. To set the `PENTAHO_JAVA_HOME` variable do these things.
 - a) In the **System Variable** section, click **New**.
 - b) In the window that appears, type `PENTAHO_JAVA_HOME` in the **Variable Name** field.
 - c) In the **Variable value** field, enter the directory where your Oracle JDK or Oracle JRE is installed. For example your Java JRE is in the `Program Files\Java\jre7` directory, type this.

```
C:\Program Files\Java\jre7
```

- d) Click **OK**. Click **OK** again to exit from the **Environment Variables** window, and then click **OK** one last time to exit from the **System Properties** window.
5. Log out, then log back in.
 6. To verify that the variables have been properly set, open a **Command Prompt** window and type this.

```
echo %PENTAHO_JAVA_HOME%
```

7. The supported Java version should appear.

Set Linux PENTAHO_JAVA_HOME Variable

1. Open a **terminal** window and log in as **root**.
2. Open the `/etc/environment` file with a text editor.

Note: The `vi` and `gedit` text editors are available on most Linux machines. For example, to open the `/etc/environment` file with `gedit`, type this.

```
gedit /etc/environment
```

3. Indicate where you installed Java in your `/etc/environment` file by typing this.

Note: Substitute `/usr/lib/jvm/java-7-sun` with the location of the JRE or JDK you installed on your system.

```
export PENTAHO_JAVA_HOME=/usr/lib/jvm/java-7-sun
```

4. Save and close the file.
5. Log out, then log back in for the change to take effect.
6. Verify that the variables are properly set by opening a **Terminal** window and typing this.

```
env | grep PENTAHO_JAVA_HOME
```

7. The supported Java version should appear.


Adjust Amount of Memory Mac OS Allocates for PostgreSQL

If you plan to install the software on a Mac OS, and you choose to use PostgreSQL, you need to increase the amount of memory that the Mac OS allocates for PostgreSQL. You can skip these instructions if you plan to install the software on Windows or Linux.

PostgreSQL is the name of the default database that contains audit, schedule and other data that you create.

PostgreSQL starts successfully only if your computer has allocated enough memory. Go to <http://www.postgresql.org/docs/devel/static/kernel-resources.html> and follow the instructions there on how to adjust the memory settings on your computer.

Initialize Repository



Before you prepare the BA Repository complete the tasks in [Prepare Environment](#).

Pentaho stores content about reports that you create, examples we provide, report scheduling data, and audit data in the BA Repository. The BA Repository resides on the database that you installed during the Prepare Environment step. The BA Repository consists of three repositories: *Jackrabbit*, *Quartz*, and *Hibernate*.

- *Jackrabbit* contains the solution repository, examples, security data, and content data from reports that you use Pentaho software to create.
- *Quartz* holds data that is related to scheduling reports and jobs.
- *Hibernate* holds data that is related to audit logging.

This step only consists of one task: Initialize the database. In this task you run DDLs that contain SQL commands that create the Jackrabbit, Quartz, and Hibernate databases, as well as the Operations Mart schema.

- [Initialize PostgreSQL](#)
- [Initialize MySQL](#)
- [Initialize Oracle](#)

Initialize PostgreSQL BA Repository Database

To initialize PostgreSQL so that it serves as the BA Repository, run SQL scripts to create the Hibernate, Quartz and Jackrabbit (also known as the JCR) databases.

Note: Your PostgreSQL configuration must support logins from all users. This is not always the default configuration, so you may have to edit your `pg_hba.conf` file to support this option. If you do need to make changes to `pg_hba.conf`, you must restart the PostgreSQL server before proceeding.

1. To make the databases that you create more secure, Pentaho recommends that you change the default passwords in the SQL script files to ones that you specify. If you are evaluating Pentaho, you might want to skip this step. If you do decide to make the databases more secure, use a text editor to change the passwords in these files:
 - `pentaho/server/biserver-ee/data/postgresql/create_jcr_postgresql.sql`
 - `pentaho/server/biserver-ee/data/postgresql/create_quartz_postgresql.sql`
 - `pentaho/server/biserver-ee/data/postgresql/create_repository_postgresql.sql`

Here is an example of a password change made in the `create_jcr_postgresql.sql` file.

```
CREATE USER jcr_user PASSWORD 'myNewPassword'
```

2. **Windows:** The commands you use to run the SQL scripts depends on your operating system. For windows, do this.
 - a) Open a **SQL Shell** window. The **SQL Shell** window is installed with PostgreSQL.
 - b) When prompted for the server enter the name of the server if you are not using the default (localhost). If you are using the default, do not type anything and press Enter.
 - c) When prompted for the database enter the name of the database if you are not using the default (postgres) If you are using the default, do not type anything and press Enter.
 - d) When prompted for the port enter the name of the port if you are not using the default (5432). If you are using the default port, do not type anything and press Enter.
 - e) When prompted for the username, accept the default, then press Enter.
 - f) When prompted for the password, enter the password that you indicated when you installed PostgreSQL.
 - g) Run the script to create the Jackrabbit database by typing this.

```
\i /pentaho/server/biserver-ee/data/postgresql/create_jcr_postgresql.sql
```

Note:If necessary, change the `\pentaho\server\biserver-ee` to the place where you unpacked your pentaho files.

- h) Run the script to create the hibernate database by typing this.

```
\i /pentaho/server/biserver-ee/data/postgresql/create_repository_postgresql.sql
```

- i) Run the script to create the Quartz database by typing this.

```
\i /pentaho/server/biserver-ee/data/postgresql/create_quartz_postgresql.sql
```

- j) To switch to the Hibernate database, type this.

```
\c postgres
```

- k) Run the script to create the Operations Mart database by typing this.

```
\i /pentaho/server/biserver-ee/data/postgresql/pentaho_mart_postgresql.sql
```

- l) Exit from the window by pressing the **CTRL + C** keys.

3. Linux: To run the SQL scripts on a Linux system, do this.

- Open a **Terminal** window. You should be logged in as the **pentaho** user.
- Sign into PostgreSQL by typing `psql -U postgres -h localhost` at the prompt.
- Run the script to create the Jackrabbit database by typing this.

```
\i ~/pentaho/server/biserver-ee/data/postgresql/create_jcr_postgresql.sql
```

Note:If necessary, change the `~/pentaho/server/biserver-ee` directory path to the place where you unpacked your pentaho files.

- d) Run the script to create the hibernate database by typing this.

```
\i ~/pentaho/server/biserver-ee/data/postgresql/create_repository_postgresql.sql
```

Note:If necessary, change the `~/pentaho/server/biserver-ee` to the place where you unpacked your pentaho files.

- e) Run the script to create the Quartz database by typing this.

```
\i ~/pentaho/server/biserver-ee/data/postgresql/create_quartz_postgresql.sql
```

Note:If necessary, change the `~/pentaho/server/biserver-ee` directory path to the place where you unpacked your pentaho files.

- f) To switch to the Hibernate database, type this.

```
\c postgres
```

- g) Run the script to create the Operations Mart database by typing this.

```
\i ~/pentaho/server/biserver-ee/data/postgresql/pentaho_mart_postgresql.sql
```

- h) Exit from the window by pressing the **CTRL + C** keys.

4. To verify that databases and user roles have been created, do this.

- Open the pgAdminIII tool. pgAdminIII is bundled with both the Windows and Linux versions of PostgreSQL.
- To view the contents of PostgreSQL, click the PostgreSQL folder in the **Object Browser**, then enter the password when prompted.
- In the **Object Browser**, click the **Databases** folder. The Jackrabbit, Postgres, Hibernate and Quartz databases should appear.
- In the **Object Browser**, click the **Login Roles** folder. The `jcr_user`, `pentaho_user`, `hibuser`, and `postgres` user accounts appear.
- If the databases and login roles do not appear, go to the beginning of these instructions and try running the scripts again.
- Select **File > Exit** to exit from pgAdminIII.

Initialize MySQL BA Repository Database

To initialize MySQL so that it serves as the BA Repository, run SQL scripts to create the Hibernate, Quartz and Jackrabbit (also known as the JCR) databases.

Note: Use the ASCII character set when you run these scripts. Do not use UTF-8 because there are text string length limitations that might cause the scripts to fail.

1. To make the databases that you create more secure, Pentaho recommends that you change the default passwords in the SQL script files to ones that you specify. If you are evaluating Pentaho, you might want to skip this step. If you do decide to make the databases more secure, use a text editor to change the passwords in these files:

- `pentaho/server/biserver-ee/data/mysql5/create_jcr_mysql.sql`
- `pentaho/server/biserver-ee/data/mysql5/create_quartz_mysql.sql`
- `pentaho/server/biserver-ee/data/mysql5/create_repository_mysql.sql`

Here is an example of a password change made in the `create_jcr_mysql.sql` file.

```
grant all on jackrabbit.* to 'jcr_user'@'localhost' identified by 'myNewPassword';
```

2. The process for running the SQL scripts against MySQL are the same for both Windows and Linux machines.
 - a) Run the `create_quartz_mysql.sql` script in the **Terminal** or **Command Prompt** window by typing: `mysql -u root -p < create_quartz_mysql.sql`.
 - b) Run the `create_repository_mysql.sql` script in the **Terminal** or **Command Prompt** window by typing: `mysql -u root -p < create_repository_mysql.sql`.
 - c) Run the `create_jcr_mysql.sql` script in the **Terminal** or **Command Prompt** window by typing: `mysql -u root -p < create_jcr_mysql.sql`.
 - d) Run the `pentaho_mart_mysql.sql` script in the **Terminal** or **Command Prompt** window by typing: `mysql -u root -p < pentaho_mart_mysql.sql`.
3. To verify that databases and user roles have been created, do this.
 - a) Open the **MySQL Workbench** tool. **MySQL Workbench** is freely available at the MySQL development site.
 - b) Make sure that the Jackrabbit (JCR), Hibernate, and Quartz databases are present.
 - c) Make sure that the `jcr_user`, `hibuser`, and `pentaho_user` user accounts are present.
 - d) If the databases and login roles do not appear, go to the beginning of these instructions and try running the scripts again.
 - e) Exit from the **MySQL Workbench**.

Initialize Oracle BA Repository Database

To initialize Oracle so it serves as the BA Repository, run SQL scripts to create the Hibernate, Quartz and Jackrabbit (also known as the JCR) databases.

1. To make the databases that you create more secure, Pentaho recommends that you change the default passwords in the SQL script files to ones that you specify. If you are evaluating Pentaho, you might want to skip this step. If you do decide to make the databases more secure, use a text editor to change the passwords in these files. (Also, for each file, edit the `datafile` path with the path to your Oracle installation.)

- `pentaho/server/biserver-ee/data/oracle10g/create_jcr_ora.sql`
- `pentaho/server/biserver-ee/data/oracle10g/create_quartz_ora.sql`
- `pentaho/server/biserver-ee/data/oracle10g/create_repository_ora.sql`

Here is an example of a password change made in the `create_jcr_ora.sql` file.

```
--conn admin/myNewPassword@pentaho
create user jcr_user identified by "myNewPassword" default tablespace
pentaho_tablespace quota unlimited on pentaho_tablespace temporary tablespace temp
quota 5M on system;
```

2. Although there are several different methods for running SQL scripts, these instructions explain how to run SQL*Plus from a **Terminal** or **Command Prompt** window. These instructions are the same for both Windows and Linux. If you prefer to run SQL scripts using another method, modify instructions accordingly.
 - a) Open a **Terminal** or **Command Prompt** window, start the **SQL*Plus** and log in.
 - b) Run the script to create the Jackrabbit database by typing `START create_jcr_ora`. If necessary, append the path to the `create_jcr_ora.sql` path in the command.
 - c) Run the script to create the repository database by typing `START create_repository_ora`. If necessary, append the path to the `create_repository_ora.sql` path in the command.
 - d) Run the script to create the Quartz database and users by typing `START create_quartz_ora`. If necessary, append the path to the `create_quartz_ora.sql` path in the command.
 - e) Run the script to create the Operations Mart database and users by typing `START pentaho_mart_ora`. If necessary, append the path to the `pentaho_mart_ora.sql` path in the command.
3. To verify that databases and user roles have been created, do this.
 - a) In the **Terminal** or **Command Prompt** window that is running **SQL*Plus**, make sure that the Jackrabbit database has been created by typing `DESCRIBE JACKRABBIT;`. The column definitions should appear when you press **Enter**.
 - b) Make sure the Quartz database has been created by typing `DESCRIBE QUARTZ;`. The column definitions for the Quartz table should appear when you press **Enter**.
 - c) To see the users that have been created, type `SELECT USERNAME FROM DBA_USERS`.
 - d) If the databases and login roles do not appear, go to the beginning of these instructions and try running the scripts again.
 - e) Exit from **SQL*Plus**.

Configure Repository



Before you configure the BA Repository complete the tasks in [Initialize Repository](#).

Tasks performed during this step include configuring Audit, Quartz, and Hibernate properties. Tasks are grouped by the BA Repository database you have.

- [PostgreSQL Configuration Tasks](#)
- [MySQL Configuration Tasks](#)
- [Oracle Configuration Tasks](#)

Configure PostgreSQL BA Repository Database

These instructions explain how to configure Quartz, Hibernate, Jackrabbit, and Pentaho Security for use with the PostgreSQL database. By default, the files edited in this section are configured for a PostgreSQL database that runs on port 5432. The default password is also in these files. If you have a different port, different password, or if had the system configured using a different database and now you want to change it back to PostgreSQL, complete all of the instructions in these steps.

Configure Quartz on PostgreSQL BA Repository Database

When you use Pentaho to schedule an event, such as a report to be run every Sunday at 1:00 a.m. EST, event information is stored in the Quartz JobStore. During the installation process, you must indicate where the JobStore is located. To do this, modify the `quartz.properties` file.

1. Open the `pentaho/server/biserver-ee/pentaho-solutions/system/quartz/quartz.properties` file in the text editor of your choice.
2. Make sure that in the `#_replace_jobstore_properties` section of the file, the `org.quartz.jobStore.driverDelegateClass` is set to `org.quartz.impl.jdbcjobstore.PostgreSQLDelegate`.
3. In the `# Configure Datasources` section of the file, set the `org.quartz.dataSource.myDS.jndiURL` equal to `quartz`, like this.

```
org.quartz.dataSource.myDS.jndiURL = quartz
```

4. Save the file and close the text editor.

Configure Hibernate Settings for PostgreSQL BA Repository Database

Modify the hibernate settings file to specify where Pentaho will find the BA Repository's hibernate configuration file. The hibernate configuration file specifies driver and connection information, as well as dialects and how to handle connection closes and timeouts.

1. Open `pentaho/server/biserver-ee/pentaho-solutions/system/hibernate/hibernate.settings.xml` in a text editor.
2. Verify that the location of the PostgreSQL hibernate configuration file appears. Make changes if necessary.

```
<config-file>system/hibernate/postgresql.hibernate.cfg.xml</config-file>
```

3. Save the file if you had to make changes, then close it. Otherwise, just close it.
4. Open `pentaho/server/biserver-ee/pentaho-solutions/system/hibernate/postgresql.hibernate.cfg.xml` in a text editor.
5. Make sure that the password and port number match the ones you specified in your configuration. Make changes as necessary, then save and close the file.

Modify Jackrabbit BA Repository Information for PostgreSQL

Indicate which database houses the BA Repository as well as the port, url, username, and password. All of the information needed to configure the repository for the PostgreSQL, MySQL, and Oracle BA Repository databases appear. By default, the PostgreSQL sections are not commented out, but the MySQL and Oracle sections are. To modify this file so that it works for your BA Repository, you will need to make sure that the sections that refer to your BA Repository database are not commented out, and the sections refer to other BA Repository databases are commented out.

When code is commented out, it appears between the `<!--` and `-->` tags. The information in between the tags is commented out, and is therefore not executed by the software. In this example, the code `<!-- <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">` is commented out.

```
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
-->
```

To make sure that the Jackrabbit repository is set so that PostgreSQL is the default database, do this.

1. Use a text editor to open the `pentaho/server/biserver-ee/pentaho-solutions/system/jackrabbit/repository.xml` file.
2. In the Repository part of the code, make sure that the PostgreSQL lines of code are not commented out, but the Oracle and MySQL lines are. The code should look like this.

```
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
  <param name="driver" value="com.mysql.jdbc.Driver"/>
  ...
  <param name="schemaObjectPrefix" value="fs_repos_"/>
</FileSystem>
<FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
  <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
  ...
  <param name="schemaObjectPrefix" value="fs_repos_"/>
  <param name="tablespace" value="jackrabbit"/>
</FileSystem>
-->
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
  <param name="driver" value="org.postgresql.Driver"/>
  <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
  <param name="user" value="jcr_user"/>
  <param name="password" value="password"/>
  <param name="schema" value="postgresql"/>
  <param name="schemaObjectPrefix" value="fs_repos_"/>
</FileSystem>
```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

3. In the DataStore section of the code, verify that the PostgreSQL lines of code are not commented out, but the Oracle and MySQL lines are. The code should look like this.

```
<!--
<DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="ds_repos_"/>
</DataStore>
<DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
  <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
  ...
  <param name="schemaObjectPrefix" value="ds_repos_"/>
</DataStore>
-->
<DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
  <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
```



```

<param name="driver" value="org.postgresql.Driver"/>
<param name="user" value="jcr_user"/>
<param name="password" value="password"/>
<param name="databaseType" value="postgresql"/>
<param name="minRecordLength" value="1024"/>
<param name="maxConnections" value="3"/>
<param name="copyWhenReading" value="true"/>
<param name="tablePrefix" value=""/>
<param name="schemaObjectPrefix" value="ds_repos_"/>
</DataStore>

```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

4. In the Workspaces section of the code, make sure that the PostgreSQL lines of code are not commented out, but the Oracle and MySQL lines are. This code should look like this.

```

<!--
  <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
    <param name="driver" value="com.mysql.jdbc.Driver"/>
    ...
    <param name="schemaObjectPrefix" value="fs_ws_"/>
  </FileSystem>
  <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
    <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
    ...
    <param name="schemaObjectPrefix" value="fs_ws_"/>
    <param name="tablespace" value="jcr_user"/>
  </FileSystem>
-->
  <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
    <param name="driver" value="org.postgresql.Driver"/>
    <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
    <param name="user" value="jcr_user"/>
    <param name="password" value="password"/>
    <param name="schema" value="postgresql"/>
    <param name="schemaObjectPrefix" value="fs_ws_"/>
  </FileSystem>

```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

5. In the Persistence Manager section of the code, verify that the PostgreSQL lines of code are not commented out, but the Oracle and MySQL lines are. The code should look like this.

```

<!--
  <PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.MySqlPersistenceManager">
    <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
    ...
    <param name="schemaObjectPrefix" value="{wsp.name}_pm_ws_"/>
  </PersistenceManager>
  <PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.OraclePersistenceManager">
    <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
    ...
    <param name="schemaObjectPrefix" value="{wsp.name}_pm_ws_"/>
    <param name="tablespace" value="jackrabbit"/>
  </PersistenceManager>
-->
  <PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.PostgreSQLPersistenceManager">
    <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
    <param name="driver" value="org.postgresql.Driver"/>
    <param name="user" value="jcr_user"/>
    <param name="password" value="password"/>
    <param name="schema" value="postgresql"/>
    <param name="schemaObjectPrefix" value="{wsp.name}_pm_ws_"/>
  </PersistenceManager>

```

```
</PersistenceManager>
```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

6. In the Versioning section of the code, verify that the PostgreSQL lines of code are not commented out, but the MySQL and Oracle lines are. The code should look like this.

```
<!--
  <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
    <param name="driver" value="com.mysql.jdbc.Driver"/>
    ...
    <param name="schemaObjectPrefix" value="fs_ver_"/>
  </FileSystem>
  <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
    <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
    ...
    <param name="schemaObjectPrefix" value="fs_ver_"/>
    <param name="tablespace" value="jackrabbit"/>
  </FileSystem>
-->
  <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
    <param name="driver" value="org.postgresql.Driver"/>
    <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
    <param name="user" value="jcr_user"/>
    <param name="password" value="password"/>
    <param name="schema" value="postgresql"/>
    <param name="schemaObjectPrefix" value="fs_ver_"/>
  </FileSystem>
```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

7. In the Persistence Manager section of the code that is near the end of the file, verify that PostgreSQL lines of code are not commented out, but the MySQL and Oracle lines are. The codes should look like this.

```
<!--
  <PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.MySqlPersistenceManager">
    <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
    ...
    <param name="schemaObjectPrefix" value="pm_ver_"/>
  </PersistenceManager>

  <PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.OraclePersistenceManager">
    <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
    ...
    <param name="schemaObjectPrefix" value="pm_ver_"/>
    <param name="tablespace" value="jackrabbit"/>
  </PersistenceManager>
-->
  <PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.PostgreSQLPersistenceManager">
    <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
    <param name="driver" value="org.postgresql.Driver"/>
    <param name="user" value="jcr_user"/>
    <param name="password" value="password"/>
    <param name="schema" value="postgresql"/>
    <param name="schemaObjectPrefix" value="pm_ver_"/>
  </PersistenceManager>
```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

8. Close and save the file.

Prepare MySQL BA Repository Database

These instructions explain how to configure Quartz, Hibernate, Jackrabbit, and Pentaho Security for a MySQL database. By default, the examples in this section are for a MySQL database that runs on port 3306. The default password is also in these examples. If you have a different port, different password complete all of the instructions in these steps.

Configure Quartz on MySQL BA Repository Database

When you use Pentaho to schedule an event, such as a report to be run every Sunday at 1:00 a.m. EST, event information is stored in the Quartz JobStore. During the installation process, you must indicate where the JobStore is located. To do this, modify the `quartz.properties` file.

1. Open the `pentaho/server/biserver-ee/pentaho-solutions/system/quartz/quartz.properties` file in the text editor of your choice.
2. In the `#{_replace_jobstore_properties}` section of the file, set the `org.quartz.jobStore.driverDelegateClass` equal to `org.quartz.impl.jdbcjobstore.StdJDBCDelegate`.
`org.quartz.jobStore.driverDelegateClass = org.quartz.impl.jdbcjobstore.StdJDBCDelegate`
3. Save the file and close the text editor.

Configure Hibernate Settings for MySQL

Modify the hibernate settings file to specify where Pentaho will find the BA Repository's hibernate configuration file. The hibernate configuration file specifies driver and connection information, as well as dialects and how to handle connection closes and timeouts.

1. Open `pentaho/server/biserver-ee/pentaho-solutions/system/hibernate/hibernate.settings.xml` in a text editor. By default, system indicates the location of the PostgreSQL hibernate configuration file.

```
<config-file>system/hibernate/postgresql.hibernate.cfg.xml</config-file>
```

2. Change the default reference to the MySQL configuration file.

```
<config-file>system/hibernate/mysql5.hibernate.cfg.xml</config-file>
```

3. Save and close the file.
4. Open `pentaho/biserver-ee/pentaho/solutions/system/hibernate/mysql5.hibernate.cfg.xml` in a text editor.
5. Make sure that the password and port number match the ones you specified in your configuration. Make changes as necessary, then save and close the file.

Modify Jackrabbit Repository Information for MySQL

You must indicate which database is used as the BA Repository as well as the port, url, username, and password. All of the information needed to configure the repository for the PostgreSQL, MySQL, and Oracle BA Repository databases appear. By default, the PostgreSQL sections are not commented out, but the MySQL and Oracle sections are. To modify this file so that it works for your BA Repository, you will need to make sure that the sections that refer to your BA Repository Database are not commented out, and the sections refer to other BA Repository databases are commented out.

When code is commented out, it appears between the `<!--` and `-->` tags. The information in between the tags is commented out, and is therefore not executed by the software. In this example, the code `<!-- <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">` is commented out.

```
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
-->
```

To modify the Jackrabbit repository so that MySQL is the default database, do this.

1. Use a text editor to open the `pentaho/server/biserver-ee/pentaho-solutions/system/jackrabbit/repository.xml` file.
2. In the Repository part of the code, change the code so that the MySQL lines of code are not commented out, but the PostgreSQL and Oracle lines are, like this.

```
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
  <param name="driver" value="com.mysql.jdbc.Driver"/>
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
  <param name="user" value="jcr_user"/>
  <param name="password" value="password"/>
  <param name="schema" value="mysql"/>
  <param name="schemaObjectPrefix" value="fs_repos_"/>
</FileSystem>
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
  <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
  ...
  <param name="schemaObjectPrefix" value="fs_repos_"/>
  <param name="tablespace" value="jackrabbit"/>
</FileSystem>

<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
  <param name="driver" value="org.postgresql.Driver"/>
  ...
  <param name="schemaObjectPrefix" value="fs_repos_"/>
</FileSystem>
-->
```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

3. In the DataStore section of the code, change the code so that the MySQL lines of code are not commented out, but the PostgreSQL and Oracle lines are, like this.

```
<DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
  <param name="user" value="jcr_user"/>
  <param name="password" value="password"/>
  <param name="databaseType" value="mysql"/>
  <param name="driver" value="com.mysql.jdbc.Driver"/>
  <param name="minRecordLength" value="1024"/>
  <param name="maxConnections" value="3"/>
  <param name="copyWhenReading" value="true"/>
  <param name="tablePrefix" value=""/>
  <param name="schemaObjectPrefix" value="ds_repos_"/>
</DataStore>
<!--
<DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
  <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
  ...
  <param name="schemaObjectPrefix" value="ds_repos_"/>
</DataStore>
<DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
  <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="ds_repos_"/>
</DataStore>
-->
```

4. In the Workspaces section of the code, change the code so that the MySQL lines of code are not commented out, but the PostgreSQL and Oracle lines are, like this.

```
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
  <param name="driver" value="com.mysql.jdbc.Driver"/>
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
  <param name="user" value="jcr_user"/>
  <param name="password" value="password"/>
  <param name="schema" value="mysql"/>
```

```

    <param name="schemaObjectPrefix" value="fs_ws_" />
  </FileSystem>
<!--
  <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
    <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE" />
    ...
    <param name="schemaObjectPrefix" value="fs_ws_" />
    <param name="tablespace" value="jcr_user" />
  </FileSystem>
  <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
    <param name="driver" value="org.postgresql.Driver" />
    ...
    <param name="schemaObjectPrefix" value="fs_ws_" />
  </FileSystem>
-->

```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

5. In the Persistence Manager section of the code, change the code so that the MySQL lines of code are not commented out, but the PostgreSQL and Oracle lines are, like this.

```

<PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.MySqlPersistenceManager">
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit" />
  <param name="user" value="jcr_user" />
  <param name="password" value="password" />
  <param name="schema" value="mysql" />
  <param name="schemaObjectPrefix" value="${wsp.name}_pm_ws_" />
</PersistenceManager>
<!--
  <PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.OraclePersistenceManager">
  <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE" />
  ...
  <param name="schemaObjectPrefix" value="${wsp.name}_pm_ws_" />
  <param name="tablespace" value="jackrabbit" />
</PersistenceManager>
  <PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.PostgreSQLPersistenceManager">
  <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit" />
  ...
  <param name="schemaObjectPrefix" value="${wsp.name}_pm_ws_" />
</PersistenceManager>
-->

```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

6. In the Versioning section of the code, change the code so that the MySQL lines of code are not commented out, but the PostgreSQL and Oracle lines are, like his.

```

<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
  <param name="driver" value="com.mysql.jdbc.Driver" />
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit" />
  <param name="user" value="jcr_user" />
  <param name="password" value="password" />
  <param name="schema" value="mysql" />
  <param name="schemaObjectPrefix" value="fs_ver_" />
</FileSystem>
<!--
  <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
    <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE" />
    ...
    <param name="schemaObjectPrefix" value="fs_ver_" />
    <param name="tablespace" value="jackrabbit" />
  </FileSystem>
  <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
    <param name="driver" value="org.postgresql.Driver" />

```

```

    ...
    <param name="schemaObjectPrefix" value="fs_ver_" />
  </FileSystem>
-->

```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

7. In the Persistence Manager section of the code that is near the end of the file, change the code so that the MySQL lines of code are not commented out, but the PostgreSQL and Oracle lines are, like this.

```

<PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.MySqlPersistenceManager">
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit" />
  <param name="user" value="jcr_user" />
  <param name="password" value="password" />
  <param name="schema" value="mysql" />
  <param name="schemaObjectPrefix" value="pm_ver_" />
</PersistenceManager>
<!--
  <PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.OraclePersistenceManager">
  <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE" />
  ...
  <param name="schemaObjectPrefix" value="pm_ver_" />
  <param name="tablespace" value="jackrabbit" />
</PersistenceManager>
  <PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.PostgreSQLPersistenceManager">
  <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit" />
  ...
  <param name="schemaObjectPrefix" value="pm_ver_" />
</PersistenceManager>
-->

```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

Prepare Oracle BA Repository Database

These instructions explain how to configure Quartz, Hibernate, Jackrabbit, and Pentaho Security. By default, the examples in this section are for a Oracle database that runs on port 1521. The default password is also in these examples. If you have a different port, different password complete all of the instructions in these steps.

Configure Quartz on Oracle BA Repository Database

When you use Pentaho to schedule an event, such as a report to be run every Sunday at 1:00 a.m. EST, event information is stored in the Quartz JobStore. During the installation process, you must indicate where the JobStore is located. To do this, modify the `quartz.properties` file.

1. Open the `pentaho/server/biserver-ee/pentaho-solutions/system/quartz/quartz.properties` file in the text editor of your choice.
2. In the `#_replace_jobstore_properties` section of the file, set the `org.quartz.jobStore.driverDelegateClass` equal to `org.quartz.impl.jdbcjobstore.oracle.OracleDelegate`.
`org.quartz.jobStore.driverDelegateClass =`
`org.quartz.impl.jdbcjobstore.oracle.OracleDelegate`
3. Save the file and close the text editor.

Configure Hibernate Settings for Oracle

Modify the hibernate settings file to specify where Pentaho will find the BA Repository's hibernate configuration file. The hibernate configuration file specifies driver and connection information, as well as dialects and how to handle connection closes and timeouts.

1. Open `pentaho/biserver-ee/pentaho-solutions/systems/hibernate/hibernate.settings.xml` in a text editor. By default, system indicates the location of the PostgreSQL hibernate configuration file.

```
<config-file>system/hibernate/postgresql.hibernate.cfg.xml</config-file>
```

2. Change the default to this to point to the Oracle configuration file.

```
<config-file>system/hibernate/oracle10g.hibernate.cfg.xml</config-file>
```

3. Save and close the file.
4. Open `pentaho/biserver-ee/systems/hibernate/oracle10g.hibernate.cfg.xml` in a text editor.
5. Make sure that the password and port number match the ones you specified in your configuration. Make changes as necessary, then save and close the file.

Modify Jackrabbit Repository Information for Oracle

You must indicate which database is used as the BA Repository as well as the port, url, username, and password. All of the information needed to configure the repository for the PostgreSQL, MySQL, and Oracle BA Repository databases appear. By default, the PostgreSQL sections are not commented out, but the MySQL and Oracle sections are. To modify this file so that it works for your BA Repository, you will need to make sure that the sections that refer to your BA Repository Database are not commented out, and the sections refer to other BA Repository databases are commented out.

When code is commented out, it appears between the `<!--` and `-->` tags. The information in between the tags is commented out, and is therefore not executed by the software. In this example, the code `<!-- <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">` is commented out.

```
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
-->
```

To modify the Jackrabbit repository so that Oracle is the default database, do this.

1. Use a text editor to open the `pentaho/server/biserver-ee/pentaho-solutions/system/jackrabbit/repository.xml` file.
2. In the Repository part of the code, change the code so that the Oracle lines of code are not commented out, but the PostgreSQL and MySQL lines are, like this.

```
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
  <param name="driver" value="com.mysql.jdbc.Driver"/>
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="fs_repos_"/>
</FileSystem>
-->
<FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
  <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
  <param name="user" value="jcr_user"/>
  <param name="password" value="password"/>
  <param name="schemaObjectPrefix" value="fs_repos_"/>
  <param name="tablespace" value="jackrabbit"/>
</FileSystem>
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
  <param name="driver" value="org.postgresql.Driver"/>
  <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="fs_repos_"/>
</FileSystem>
-->
```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

3. Change `<param name="tablespace" value="jackrabbit"/>` to `<param name="tablespace" value="pentaho_tablespace"/>`.
4. In the DataStore section of the code, change the code so that the Oracle lines of code are not commented out, but the PostgreSQL and MySQL lines are, like this.

```

<!--
<DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="ds_repos_"/>
</DataStore>
-->
<DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
<param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
<param name="driver" value="oracle.jdbc.OracleDriver"/>
<param name="user" value="jcr_user"/>
<param name="password" value="password"/>
<param name="databaseType" value="oracle"/>
<param name="minRecordLength" value="1024"/>
<param name="maxConnections" value="3"/>
<param name="copyWhenReading" value="true"/>
<param name="tablePrefix" value=""/>
<param name="schemaObjectPrefix" value="ds_repos_"/>
</DataStore>
<!--
<DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
  <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="ds_repos_"/>
</DataStore>

```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

5. In the Workspaces section of the code, change the code so that the Oracle lines of code are not commented out, but the PostgreSQL and MySQL lines are, like this.

```

<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
  <param name="driver" value="com.mysql.jdbc.Driver"/>
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="fs_ws_"/>
</FileSystem>
-->
<FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
  <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
  <param name="user" value="jcr_user"/>
  <param name="password" value="password"/>
  <param name="schemaObjectPrefix" value="fs_ws_"/>
  <param name="tablespace" value="jcr_user"/>
</FileSystem>
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
  <param name="driver" value="org.postgresql.Driver"/>
  <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="fs_ws_"/>
</FileSystem>
-->

```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

6. Change `<param name="tablespace" value="jackrabbit"/>` to `<param name="tablespace" value="pentaho_tablespace"/>`.

7. In the Persistence Manager section of the code, change the code so that the Oracle lines of code are not commented out, but the PostgreSQL and MySQL lines are, like this.

```

<!--
<PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.MySqlPersistenceManager">
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="{wsp.name}_pm_ws_"/>
</PersistenceManager>
-->
<PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.OraclePersistenceManager">
  <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
  <param name="driver" value="oracle.jdbc.OracleDriver"/>
  <param name="user" value="jcr_user"/>
  <param name="password" value="password"/>
  <param name="schema" value="oracle"/>
  <param name="schemaObjectPrefix" value="{wsp.name}_pm_ws_"/>
  <param name="tablespace" value="jackrabbit"/>
</PersistenceManager>
<!--
<PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.PostgreSQLPersistenceManager">
  <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="{wsp.name}_pm_ws_"/>
</PersistenceManager>
-->

```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

8. Change `<param name="tablespace" value="jackrabbit"/>` to `<param name="tablespace" value="pentaho_tablespace"/>`.
9. In the Versioning section of the code, change the code so that the Oracle lines of code are not commented out, but the PostgreSQL and MySQL lines are, like his.

```

<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
  <param name="driver" value="com.mysql.jdbc.Driver"/>
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="fs_ver_"/>
</FileSystem>
-->
<FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
  <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
  <param name="user" value="jcr_user"/>
  <param name="password" value="password"/>
  <param name="schemaObjectPrefix" value="fs_ver_"/>
  <param name="tablespace" value="jackrabbit"/>
</FileSystem>
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
  <param name="driver" value="org.postgresql.Driver"/>
  <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="fs_ver_"/>
</FileSystem>
-->

```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

10. Change `<param name="tablespace" value="jackrabbit"/>` to `<param name="tablespace" value="pentaho_tablespace"/>`.

11. In the Persistence Manager section of the code that is near the end of the file, change the code so that the Oracle lines of code are not commented out, but the PostgreSQL and MySQL lines are, like this.

```


<!--
<PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.MySqlPersistenceManager">
  <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="pm_ver_"/>
</PersistenceManager>
-->
<PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.OraclePersistenceManager">
  <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
  <param name="driver" value="oracle.jdbc.OracleDriver"/>
  <param name="user" value="jcr_user"/>
  <param name="password" value="password"/>
  <param name="schema" value="oracle"/>
  <param name="schemaObjectPrefix" value="pm_ver_"/>
  <param name="tablespace" value="jackrabbit"/>
</PersistenceManager>
<!--
  <PersistenceManager
  class="org.apache.jackrabbit.core.persistence.bundle.PostgreSQLPersistenceManager">
  <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
  ...
  <param name="schemaObjectPrefix" value="pm_ver_"/>
</PersistenceManager>
-->

```

Note: If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

12. Change `<param name="tablespace" value="jackrabbit"/>` to `<param name="tablespace" value="pentaho_tablespace"/>`.

Specify Connections



After your *repository has been configured*, you must configure the web application servers to connect to the BA Repository. In this step, JDBC and JNDI connections are made to the Hibernate, Jackrabbit, and Quartz databases. These databases were installed on your BA Repository database during the *Initialize Repository* and *Configure Repository* sections of these instructions.

By default, the BA Server software is configured to be deployed and run on the Tomcat server. As such, connections have already been specified and only the Tomcat `context.xml` file must be modified.

These tasks are performed in this step.

- [Copy JDBC Drivers](#)
- [Modify JDBC Connection Information](#)

Perform Tomcat-Specific Connection Tasks

If you plan to run the BA Server on Tomcat, you must modify JDBC Connection information.

Download and Install Repository Database JDBC Drivers

For the BA Server to connect to the BA Repository database of your choice, add the BA Repository's database JDBC driver library to the appropriate place in the web application server on which the BA Server will be deployed. The default web application server for the archive installation process is Tomcat.

1. Download a JDBC driver JAR from your database vendor or a third-party driver developer.

Due to licensing restrictions, Pentaho does not distribute the necessary JDBC driver JARs. This is why you have to download the file yourself and install it.

2. Copy the JDBC driver JAR you just downloaded to the `/tomcat/lib/` directory.

Download and Install H2 JDBC Drivers

Install the H2 JDBC driver.

1. Download the version 1.2.131 of the H2 JDBC JAR from the <http://code.google.com/p/h2database/downloads/list>.
2. Copy the JDBC driver JAR you just downloaded to the `tomcat/lib/` directory.

Modify JDBC Connection Information in the Tomcat `context.xml` File

Database connection and network information, such as the username, password, driver class information, IP address or domain name, and port numbers for your BA Repository database are stored in the `context.xml` file. Modify this file to reflect the database connection and network information to reflect your operating environment. You also modify the values for the `validationQuery` parameters in this file if you have chosen to use an BA Repository database other than PostgreSQL.

1. Consult your database documentation to determine the JDBC class name and connection string for your BA Repository database.
2. Use a text editor of your choice to open the `context.xml` file that is in the `biserver-ee\tomcat\webapps\pentaho\META-INF` directory.
3. Do one of these things.

- a) If you are using PostgreSQL as your BA Repository database, comment out the resource references that refer to other databases, such as PostgreSQL and Oracle. In the PostgreSQL sections make sure the code looks like the following, but adjust the port numbers and passwords to reflect your environment, if necessary.

```
<Resource validationQuery="select 1" url="jdbc:postgresql://
localhost:5432/di_hibernate" driverClassName="org.postgresql.Driver"
password="password" username="hibuser" maxWait="10000" maxIdle="5"
maxActive="20" factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/Hibernate"/>
<Resource validationQuery="select 1" url="jdbc:postgresql://
localhost:5432/di_hibernate" driverClassName="org.postgresql.Driver"
password="password" username="hibuser" maxWait="10000" maxIdle="5"
maxActive="20" factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/Audit"/>
<Resource validationQuery="select 1" url="jdbc:postgresql://
localhost:5432/di_quartz" driverClassName="org.postgresql.Driver"
password="password" username="pentaho_user" maxWait="10000" maxIdle="5"
maxActive="20" factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/Quartz"/>
<Resource validationQuery="select 1" url="jdbc:postgresql://
localhost:5432/hibernate" driverClassName="org.postgresql.Driver"
password="password" username="hibuser" maxWait="10000" maxIdle="5"
maxActive="20" factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/
pentaho_operations_mart"/>
<Resource validationQuery="select 1" url="jdbc:postgresql://
localhost:5432/hibernate" driverClassName="org.postgresql.Driver"
password="password" username="hibuser" maxWait="10000" maxIdle="5"
maxActive="20" factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/PDI_Operations_Mart"/>
```

- b) If you are using MySQL as your BA Repository database, comment out the resource references that refer to other databases, such as PostgreSQL and Oracle. Then, add the following code to the file if it does not already exist. Adjust the port numbers and passwords to reflect your environment, if necessary.

```
<Resource validationQuery="select 1" url="jdbc:mysql://localhost:3306/
di_hibernate" driverClassName="com.mysql.jdbc.Driver" password="password"
username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/Hibernate"/>
<Resource validationQuery="select 1" url="jdbc:mysql://localhost:3306/
di_hibernate" driverClassName="com.mysql.jdbc.Driver" password="password"
username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/Audit"/>
<Resource validationQuery="select 1" url="jdbc:mysql://localhost:3306/
di_quartz" driverClassName="com.mysql.jdbc.Driver" password="password"
username="pentaho_user" maxWait="10000" maxIdle="5" maxActive="20"
factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/Quartz"/>
<Resource validationQuery="select 1" url="jdbc:mysql://localhost:3306/
hibernate" driverClassName="com.mysql.jdbc.Driver" password="password"
username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/
pentaho_operations_mart"/>
<Resource validationQuery="select 1" url="jdbc:mysql://localhost:3306/
hibernate" driverClassName="com.mysql.jdbc.Driver" password="password"
username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/PDI_Operations_Mart"/>
```

- c) If you are using Oracle as your BA Repository database, comment out the resource references that refer to other databases such as PostgreSQL and MySQL. Then, add the following code to the file if it does not exist. Adjust the port numbers and passwords to reflect your environment, if necessary.

```
<Resource validationQuery="select 1 from dual"
url="jdbc:oracle:thin:@localhost:1521/XE"
```


```

driverClassName="oracle.jdbc.OracleDriver" password="password"
username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/Hibernate"/>
<Resource validationQuery="select 1 from dual"
url="jdbc:oracle:thin:@localhost:1521/XE"
driverClassName="oracle.jdbc.OracleDriver" password="password"
username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/Audit"/>
<Resource validationQuery="select 1 from dual"
url="jdbc:oracle:thin:@localhost:1521/XE"
driverClassName="oracle.jdbc.OracleDriver" password="password"
username="quartz" maxWait="10000" maxIdle="5" maxActive="20"
factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/Quartz"/>
<Resource validationQuery="select 1 from dual"
url="jdbc:oracle:thin:@localhost:1521/XE"
driverClassName="oracle.jdbc.OracleDriver" password="password"
username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/
pentaho_operations_mart"/>
<Resource validationQuery="select 1 from dual"
url="jdbc:oracle:thin:@localhost:1521/XE"
driverClassName="oracle.jdbc.OracleDriver" password="password"
username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/PDI_Operations_Mart"/>

```

4. Modify the username, password, driver class information, IP address (or domain name), and port numbers so they reflect the correct values for your environment.
5. Make sure that the `validationQuery` variable for your database is set to one of these.
 - **PostgreSQL:** `validationQuery="select 1"`
 - **MySQL:** `validationQuery="/* ping */ select 1"/`
 - **Oracle:** `validationQuery="select 1 from dual"`
6. Save the `context.xml` file, then close it.
7. To verify that the changes have been made and saved, do this.
 - a) View the `context.xml` file again. Make sure that the changes that you made to the file in these instructions have been saved.
 - b) Close the file.
8. To make sure that the changes that you made in the `context.xml` file take effect when Tomcat is started, navigate to the `tomcat\conf\Catalina` directory. If the `pentaho.xml` file is in the present, delete it. It will be generated again when you start the BA Server, but will contain the changes that you just made in the `context.xml` file.

Start BA Server



After you've complete the tasks in the [Prepare Environment](#), [Initialize Repository](#), and [Configure Repository](#) steps, you can start the BA Server. Complete these steps.

- [Install License Keys](#)
- [Modify Tomcat Startup Script](#)
- [Start BA Server](#)

Install BA Server License Keys

1. Download the .lic file you want to install.
2. Copy your .lic files to the BA Server.
3. Navigate to the `/license-installer/` directory.
4. Run the license installation script.
 - a) **For Linux:** Run `install_license.sh` with the `install` switch and the location and name of your .lic file as a parameter. You can specify multiple .lic files separated by spaces. Be sure to use backslashes to escape any spaces in the path or file name.


```
install_license.sh install /home/dvader/downloads/Pentaho/BI/Platform/Enterprise/Edition.lic
```
 - b) **For Windows:** Run `install_license.bat` with the `install` switch and the location and name of your license file as a parameter.


```
install_license.bat install "C:\Users\dvader\Downloads\Pentaho BA Platform Enterprise Edition.lic"
```

Modify Tomcat Startup Script

The Tomcat startup script must be modified to include the `CATALINA_OPTS` variable. `CATALINA_OPTS` indicates the amount of memory to allocate. It also indicates where Pentaho licenses are installed. Specific instructions on how to modify the startup script depend on your operating system.

Modify the Tomcat Windows Startup Script

1. Make sure the Tomcat web application server is not running by starting the Windows **Task Manager** and looking for **Tomcat** in the **Applications** tab. If the server is running, stop it.
2. Use a text editor to open the `startup.bat` file, which is in the `bin` subdirectory of the Tomcat home directory.
3. Add this line directly before the `call "%EXECUTABLE%" start %CMD_LINE_ARGS%` line, which is located near the end of the file.


```
set CATALINA_OPTS=-Xms4096m -Xmx6144m -XX:MaxPermSize=256m -
Dsun.rmi.dgc.client.gcInterval=3600000 -Dsun.rmi.dgc.server.gcInterval=3600000 -
Dpentaho.installed.licenses.file=%PENTAHO_INSTALLED_LICENSE_PATH%
```
4. Save and close the file.

Modifying the Tomcat Linux Startup Script

1. Make sure the Tomcat web application server is not running by opening a **Terminal** window and typing `ps -A` at the prompt. If the server is running, stop it.
2. Use a text editor to open the `startup.sh` file, which is in the `bin` subdirectory of the Tomcat home directory.
3. Add this line directly before the `exec "$PRGDIR"/"$EXECUTABLE" start "$@"` line near the end of the file.

```
export CATALINA_OPTS="-Xms4096m -Xmx6144m -XX:MaxPermSize=256m -  
Dsun.rmi.dgc.client.gcInterval=3600000 -Dsun.rmi.dgc.server.gcInterval=3600000 -  
Dpentaho.installed.licenses.file=$PENTAHO_INSTALLED_LICENSE_PATH"
```

4. Save and close the file.

Starting the BA Server

Windows Pentaho Archive Installation

If you used the Archive Installation, we provide individual control scripts to start and stop the BA server and BA repository. Here is where you can find the individual control scripts.

BA Repository

- The Archive Installation enables you to install either PostgreSQL, MySQL, or Oracle as the repository. Consult the documentation for the RDBMS you selected for information about starting and stopping.

The BA repository must be started before the BA Server.

BA Server

- `/pentaho/server/biserver-ee/start-pentaho.bat` and `stop-pentaho.bat`

Linux Pentaho Archive Installation

If you used the Archive Installation, Pentaho provides individual control scripts to start and stop the Tomcat application server, BA Server, and BA repository. Here is where you can find the individual control scripts.

BA Repository


- The Archive Installation enables you to install either PostgreSQL, MySQL, or Oracle as the BA repository. Consult the documentation for the RDBMS you selected for information about starting and stopping.

The BA repository must be started before the BA Server.

BA Server

- `/pentaho/server/biserver-ee/start-pentaho.sh` and `stop-pentaho.sh`

Next Steps



Now that you've installed the BA Server, do two things.

- [Install the BA design tools](#), so you can generate models and reports.
- [Configure the BA Server and design tools](#) so you can install licenses, set up datasources, and choose a security method, and more. You must install the license to log into the BA Server.

Note: If you have installed the BA Server so that you can migrate content from the old system to this one, make sure that your license keys have been installed, then view the [Upgrade BA System instructions](#).

Learn More

- [Web-Based Data Analysis, Reports, and Dashboards Tutorial using the User Console](#)