



Pentaho Business Analytics Graphical Installer Guide



This document is copyright © 2011 Pentaho Corporation. No part may be reprinted without written permission from Pentaho Corporation. All trademarks are the property of their respective owners.

Help and Support Resources

If you have questions that are not covered in this guide, or if you would like to report errors in the documentation, please contact your Pentaho technical support representative.

Support-related questions should be submitted through the Pentaho Customer Support Portal at <http://support.pentaho.com>.

For information about how to purchase support or enable an additional named support contact, please contact your sales representative, or send an email to sales@pentaho.com.

For information about instructor-led training on the topics covered in this guide, visit <http://www.pentaho.com/training>.

Limits of Liability and Disclaimer of Warranty

The author(s) of this document have used their best efforts in preparing the content and the programs contained in it. These efforts include the development, research, and testing of the theories and programs to determine their effectiveness. The author and publisher make no warranty of any kind, express or implied, with regard to these programs or the documentation contained in this book.

The author(s) and Pentaho shall not be liable in the event of incidental or consequential damages in connection with, or arising out of, the furnishing, performance, or use of the programs, associated instructions, and/or claims.

Trademarks

Pentaho (TM) and the Pentaho logo are registered trademarks of Pentaho Corporation. All other trademarks are the property of their respective owners. Trademarked names may appear throughout this document. Rather than list the names and entities that own the trademarks or insert a trademark symbol with each mention of the trademarked name, Pentaho states that it is using the names for editorial purposes only and to the benefit of the trademark owner, with no intention of infringing upon that trademark.

Company Information

Pentaho Corporation
Citadel International, Suite 340
5950 Hazeltine National Drive
Orlando, FL 32822
Phone: +1 407 812-OPEN (6736)
Fax: +1 407 517-4575
<http://www.pentaho.com>

E-mail: communityconnection@pentaho.com

Sales Inquiries: sales@pentaho.com

Documentation Suggestions: documentation@pentaho.com


Sign-up for our newsletter: <http://community.pentaho.com/newsletter/>

Contents

| | |
|--|----|
| Installation Overview..... | 4 |
| The Pentaho Directory Structure: Graphical Installer..... | 5 |
| Installation Checklist..... | 7 |
| Prerequisites..... | 8 |
| Software Requirements..... | 8 |
| Important Note on Local User Accounts For Linux/Unix..... | 8 |
| Notes For Windows Vista, Windows 7, and Windows Server 2008..... | 9 |
| Preparing a Headless Linux or Solaris Server..... | 9 |
| Hardware Requirements..... | 10 |
| Obtaining the Pentaho Business Analytics Installation Utility..... | 11 |
| Server Installation Procedure..... | 12 |
| Using the Windows Installation Utility..... | 12 |
| Installing on Linux..... | 13 |
| Using the Linux Installation Utility..... | 13 |
| Starting the Servers At Boot Time On Linux..... | 15 |
| Using the Mac Installation Utility..... | 15 |
| Installing the Analysis Enterprise Edition Plugin..... | 16 |
| Switching to Memcached..... | 17 |
| Adding Linux and OS X Support for Printing Analyzer Geo Maps..... | 18 |
| Adding Windows Support for Printing Analyzer Geo Maps..... | 19 |
| Post-Install Configuration..... | 19 |
| Changing the Default Port Numbers..... | 20 |
| Workstation Installation Procedure..... | 21 |
| Testing and Using Your Server..... | 22 |
| Preparing for Production..... | 23 |
| Removing Pentaho Sample Data and Solutions..... | 23 |
| Switching to a Production Login Screen..... | 25 |
| Uninstalling Pentaho Business Analytics..... | 26 |
| Master Service Control Scripts From the Graphical Installer..... | 27 |
| Appendix: Default Pentaho Business Analytics Port Numbers..... | 28 |
| Troubleshooting..... | 29 |
| Evaluation Licenses are Not Granted..... | 29 |
| Compatibility Matrix: List of Supported Products..... | 30 |

Installation Overview

Pentaho provides several installation paths to meet a variety of customer needs. This procedure is the simplest, but provides the least customization. This guide explains how to use the graphical installer to perform a default installation of the latest release of the Pentaho Business Analytics Enterprise Edition.

 **Note:** There are 32-bit and 64-bit editions of this installation utility. Check the file name to ensure that you are using the intended version before you proceed.


| The Pentaho Business Analytics Installation Utility Will Provide | You Must Supply On Your Own |
|--|--|
| <p>Application server: Tomcat 6.0</p> <p>Solution database: MySQL 5.0</p> <p>BA Server:</p> <ul style="list-style-type: none">• Pentaho User Console• Analyzer• Dashboard Designer• Interactive Reporting• Pentaho Enterprise Console <p>Data preparation tools:</p> <ul style="list-style-type: none">• Schema Workbench• Pentaho Data Integration• Metadata Editor <p>Design tools:</p> <ul style="list-style-type: none">• Report Designer• Design Studio• Aggregation Designer <p>Data Integration (DI) Server</p> <p>Hadoop support for PDI</p> <p>Hive support for Pentaho Metadata</p> <p>A Sun JRE 1.6.0 on the server, and on each workstation that you will install data preparation or design tools to</p> | <p>A supported operating system:</p> <p>(See Compatibility Matrix: List of Supported Products on page 30 for detailed OS, database, and application server version information.)</p> <ul style="list-style-type: none">• Linux• Windows• OS X <p>One or more data sources:</p> <ul style="list-style-type: none">• Any JDBC-compliant database• A spreadsheet• A flat file containing comma-separated values |

If you just want to install a single design tool such as Report Designer or Data Integration, it's quicker and easier to use individual client tool archives as explained in the *Pentaho Archive-Based Installation Guide*.

This may not be the best installation path for your production environment. This procedure expects you to use the included MySQL database to store your Pentaho Business Analytics solutions, content, and schedules; the self-contained Data Integration Server, and the included Tomcat application server to host the BA Server Web application.

If you cannot use the graphical installer but would prefer not to build your own BA Server WAR file and install an application server, consult the *Pentaho Archive-Based Installation Guide*.


If you would prefer to build the application from source, if you want to use a different solution database or application server, if you plan to implement single sign-on through Central Authentication Service, or if you prefer to use your own Tomcat and MySQL instances, refer instead to the *Pentaho BA Server Manual Deployment Guide*.

 **Note:** The graphical installation procedure is most popular for pre-sales evaluation; the manual deployment process is most popular for development and production installations.

The Pentaho Directory Structure: Graphical Installer

Overview

The Pentaho Business Analytics installer lays down a specific directory structure for Pentaho software. Below is a diagram showing the entire structure, though your specific installation will be different if you only install parts of Pentaho Business Analytics.

 **Note:** This structure differs slightly from an archive-based installation or manual deployment. The graphical installer includes a Java Runtime Environment and some service control scripts.

Directory hierarchy

Below is an abridged Pentaho directory structure. The purpose of this diagram is to help you easily find some of Pentaho's important files and locations, which are explained below this diagram.

```
/pentaho
../server
../.../biserver-ee
../.../data
../.../licenses
../.../pentaho-solutions
../.../tomcat
../.../data-integration-server
../.../data
../.../licenses
../.../pentaho-solutions
../.../tomcat
../.../enterprise-console
../design-tools
../.../aggregation-designer
../.../data-integration
../.../design-studio
../.../metadata-editor
../.../report-designer
../.../schema-workbench
../common
../documentation
../java
../licenses
../mysql
../scripts
```

Top-level files

These files are found in the top-level Pentaho directory:

- **ctlscript:** (.sh or .bat) Starts, stops, restarts, and shows the status of Pentaho services.
- **installation-summary.txt:** Contains the information from the summary screen at the end of the installation process.
- **pentaho.log:** The Tomcat log file for the Pentaho Web application.
- **uninstall:** A script that removes Pentaho Business Analytics.

Locations of specific programs

- **BA Server:** /pentaho/server/biserver-ee/
- **DI Server:** /pentaho/server/data-integration-server/
- **Pentaho Enterprise Console:** /pentaho/server/enterprise-console/
- **Report Designer:** /pentaho/design-tools/report-designer/
- **Schema Workbench:** /pentaho/design-tools/schema-workbench/
- **Data Integration (PDI):** /pentaho/design-tools/data-integration/
- **Design Studio:** /pentaho/design-tools/design-studio/
- **Metadata Editor:** /pentaho/design-tools/metadata-editor/
- **Aggregation Designer:** /pentaho/design-tools/aggregation-designer/

- **Dashboard Designer:** /pentaho/server/biserver-ee/pentaho-solutions/system/dashboards/
- **Analyzer:** /pentaho/server/biserver-ee/pentaho-solutions/system/analyzer/
- **Interactive Reporting:** /pentaho/server/biserver-ee/pentaho-solutions/system/pentaho-interactive-reporting/
- **License installer:** /pentaho/server/enterprise-console/license-installer/



Note: The license installer can also be found in the report-designer, data-integration, and metadata-editor directories. All of these license installers perform the same functions, but are available in separate places to account for instances where only specific parts of Pentaho Business Analytics are installed to a particular machine. It does not matter which one you use. You can also install licenses through the Pentaho Enterprise Console.

Installation Checklist

The Installation Checklist is a concise list of instructions intended to show a high-level overview of the installation and configuration process. It also serves as a quick reference for administrators and developers who have performed several installations in the past and only need a brief rehash of the necessary steps. If you need more details than are provided in this checklist, consult the appropriate section in the verbose instruction set that comprises the rest of this guide.

| Step | Procedure | Done |
|--------|---|------|
| Step 1 | Download Pentaho Business Analytics 4.5 .exe, .bin, or .app installer from the Pentaho Customer Support Portal. | |
| Step 2 | If you are installing the BA Server and DI Server on Linux, create a local user account called pentaho , then switch to that user and run the Pentaho Business Analytics installation utility from it. If you are installing one or both of the servers on Windows Server 2008 or 7, run the installer as the Administrator user. | |
| Step 3 | Follow the on-screen instructions to install the BA Server, DI Server, and the Pentaho Enterprise Console on the machine that will act as your server. | |
| Step 4 | Log into the Pentaho Enterprise Console, which by default is located at <code>http://localhost:8088</code> | |
| Step 5 | Install Enterprise Edition keys, and establish users, roles, data sources, and any other configuration information. Use the <i>Pentaho Business Analytics Administrator's Guide</i> for assistance. | |
| Step 6 | Run the Pentaho Business Analytics installer on each workstation, and install any client tools that you have support entitlements for. | |
| Step 7 | Test the installation by accessing the BA Server from a workstation and verifying that you can log in as a normal user, and create reports and analysis views. Also access the DI Server from a Pentaho Data Integration workstation and ensure that you can create or connect to an enterprise repository. | |

Prerequisites

In order to install Pentaho Business Analytics, you should be familiar with system administration operations pertaining to network services, including modifying your firewall to open specific ports, and adding services to the system startup and shutdown scripts. In most installation scenarios, this will require you to be comfortable using your operating system's command line interface and/or graphical system administration tools. You must have the ability to install software, open firewall ports, and start and stop system services on the machine you are installing on. If you don't have the requisite access or permissions, having the cooperation of someone who does (the sysadmin or DBA) is probably good enough.

Installing Pentaho Business Analytics client tools onto end-user workstations is a much simpler process which requires little more than being able to run the graphical installation utility.

Software Requirements



Note: The graphical installation utility is much more limited than the Business Analytics software it provides. If you need to evaluate Business Analytics with a different supported configuration, contact your sales representative. For a more comprehensive list of supported software environments, refer to the appendix at the end of this guide.

- Windows (XP SP2, 2008, 7)
- Modern Linux distributions (SUSE Linux Enterprise Desktop and Server 10 and Red Hat Enterprise Linux 5 are officially supported, but most others should work)
- Mac OS X 10.5 (and newer)

The Pentaho Business Analytics installer will provide you with a Sun Java Runtime Environment (JRE) version 1.6 (sometimes referenced as version 6.0) installed. If you have other versions installed, they will be ignored.

A modern Web browser is required to access Pentaho's Web interface:

- Internet Explorer 7 or higher
- Firefox 3.6, or 9 and 10
- Safari 5
- Chrome

Your environment can be either 32-bit or 64-bit as long as it meets the above requirements.

Important Note on Local User Accounts For Linux/Unix

The section below advises you to create a local user account called **pentaho**. In this new user's home directory you will put the pentaho-solutions directory and store license information recorded by the Pentaho Enterprise Console. You will have to adjust your init scripts to start your Web application server (which will run the BA Server) and the Pentaho Enterprise Console as this user. If you are unable to do this, you must modify the instructions in the rest of this guide to support your own custom user and directory configuration.



Caution: If you do not run the Pentaho Enterprise Console and the application server that runs the BA Server as the same system user, the BA Server will not be able to find the appropriate license information and will not operate with full functionality. If you need to launch the Pentaho Enterprise Console and the BA Server as separate users or services, you will have to set a **-D** parameter in your Web application server's service configuration or startup scripts to specify a static location for your Pentaho license file. The Java parameter is **-Dpentaho.installed.licenses.file=/pentaho/installedLicenses.xml**, though you will need to change this example to match your configuration.



Caution: If you choose to put the pentaho-solutions directory in a parent directory that the pentaho user (or whatever user account you are running your Pentaho services as) does not have write access to, you will not be able to save any reports, analysis views, or dashboards, and you will not be able to set user permissions on any existing content.

Creating a Pentaho System User (Linux/Solaris)

This is for Linux, Solaris, and other Unix-like operating systems only. Windows users do not need to follow this procedure. Theoretically, you can use a different local user account than the one suggested here. However, you will have to modify all of the instructions from here onward to match that configuration.

Pentaho licenses are installed to an XML file in the home directory of the user that starts the Pentaho Enterprise Console. While you can use any system user to install licenses, it is easier to create a new user to start and stop the Pentaho Enterprise Console, and to install and update licenses with.

1. Open a local terminal on, or an OpenSSH session to the server you are hosting the BA Server on.

```
ssh pgibbons@192.168.1.133
```

2. With root permissions, create a new user account called **pentaho**.

Bash is not a requirement, but it is typically the shell that Linux users want to standardize on. On many Linux distributions, the default new user shell is `/bin/sh` or some equivalent (such as Dash) that may not use the `~/.bashrc` configuration file that you will work with later. If you don't have or want to use Bash, adjust the instructions throughout this guide accordingly.

```
sudo useradd -s /bin/bash -m pentaho
```

3. Set a password for the pentaho user (note that when using the **sudo** command, you must first supply the root password).

```
sudo passwd pentaho
```

4. Verify that you can log in using the credentials you specified.

```
su pentaho -
```

You now have a user account created specifically for running the BA Server and controlling Pentaho Enterprise Console start and stop scripts. You should stay logged into this new account to create the pentaho directory in the next section, and all other installation tasks that do not explicitly require root access.

You must use this new user account for starting and stopping the Pentaho Enterprise Console, and for installing and updating licenses if you use the command line tool to manage them instead of the graphical interface in Pentaho Enterprise Console. If you create any RC or init scripts to start Pentaho Enterprise Console automatically at boot time, then you will have to fashion those scripts such that they start the service with the **pentaho** user credentials.

Notes For Windows Vista, Windows 7, and Windows Server 2008

Windows Vista, 7, and Server 2008 have expanded user access and permissions restrictions that change the way Pentaho Analytics is installed and accessed by system users. The graphical installation utility or license installation script must be executed in with elevated permissions (**Run Elevated** status) in order for the BA Server and DI Server to be accessible to all users. This is not an issue on Windows XP or Server 2003.

Preparing a Headless Linux or Solaris Server

There are two headless server scenarios that require special procedures on Linux and Solaris systems. One is for a system that has no video card; the other is for a system that has a video card, but does not have an X server installed. In some situations -- particularly if your server doesn't have a video card -- you will have to perform both procedures in order to properly generate reports with the BA Server.

Systems without video cards

The **java.awt.headless** option enables systems without video output and/or human input hardware to execute operations that require them. To set this application server option when the BA Server starts, open the `/pentaho/server/biserver-ee/start-pentaho.sh` script with a text editor, then add the following item to the list of CATALINA_OPTS parameters: **-Djava.awt.headless=true**.

The entire line should look something like this:

```
export CATALINA_OPTS="-Djava.awt.headless=true -Xms256m -Xmx768m -XX:MaxPermSize=256m -Dsun.rmi.dgc.client.gcInterval=3600000 -Dsun.rmi.dgc.server.gcInterval=3600000"
```



Note: If you do not have an X server installed, you must also follow the below instructions.

Systems without X11

In order to generate charts, the Pentaho Reporting engine requires functionality found in X11. If you are unwilling or unable to install an X server, you can install the **xvfb** package instead. xvfb provides X11 framebuffer emulation, which performs all graphical operations in memory instead of sending them to the screen.

Use your operating system's package manager to properly install xvfb.

Hardware Requirements

Pentaho Business Analytics does not have strict limits on computer or network hardware. As long as you meet the minimum software requirements (note that your operating system will have its own minimum hardware requirements), Pentaho is hardware agnostic but there is a recommended set of minimum system specifications:

Server:

- **RAM:** at least 4GB
- **Hard drive space:** at least 2GB for the software, and more for solution and content files
- **Processor:** dual-core AMD64 or Intel EM64T

Workstation:

- **RAM:** at least 2GB
- **Hard drive space:** at least 1GB for the software, and more for solution and content files
- **Processor:** dual-core AMD64 or Intel EM64T

It's possible to use less capable machines, but in most scenarios this will result in an undesirable level of performance.

Your environment does not have to be 64-bit, even if your processor architecture supports it. All modern desktop, workstation, and server machines have 64-bit processors, but they sometimes ship by default with 32-bit operating systems. Please check with your Information Technology Department if you are unsure of your configuration. If you want to run Pentaho Business Analytics in a pure 64-bit environment, you will have to install a 64-bit operating system, ensure that your solution database and Java Runtime Environment are 64-bit, and install Pentaho Business Analytics via the 64-bit graphical installer, or through the archive-based or manual deployment methods.



Note: A 32-bit JRE has a hard memory limit of 2GB (1.5GB on Windows), so if you have 2GB or more of RAM, you must use a 64-bit JRE on a 64-bit operating system to take full advantage of it. This means that, through architectural limitations, a 32-bit environment will likely be under-powered for a production BA Server deployment.


Obtaining the Pentaho Business Analytics Installation Utility

Consult the Welcome Kit email that was sent to you after completing the sales process. This email contains user credentials for the Pentaho Customer Support Portal, and download instructions that tell you where to find the installer once you've logged in. There are self-contained installation utilities available for the Windows, Linux, and OS X platforms. You will use the same installation utility to install the BA Server, DI Server, and Pentaho Enterprise Console on your server, and the Pentaho client tools on your end-user workstations.

Server Installation Procedure


To manually install and configure the Pentaho BA Server, DI Server, and Pentaho Enterprise Console from the Pentaho Business Analytics installer, follow these procedures in the order they are presented. This process should take less than 20 minutes.

If upgrading, ensure previous versions have been uninstalled to avoid errors.

 **Note:** The installation utility is unable to process the following characters in passwords: ' " & < > \ `


Using the Windows Installation Utility

These instructions are for Windows users only. Linux users should refer to the Linux installation instructions instead.

 **Note:** You must disable any anti-spyware software before installing Pentaho Business Analytics. Some types of software firewalls and anti-virus scanners may also block the BA Server or prevent it from operating normally.


Step-by-step instructions for using the installer are below. You may need to adjust the instructions for your specific situation.

1. Run the installation utility as you would any other program - double-click it.
2. When the installation utility starts, you'll see a Pentaho splash screen. Click Next.



3. Accept the license agreement to continue.
4. When prompted for which setup type you'd like to perform, select **Default** if you want to install the entire content of Pentaho Business Analytics on one machine, or **Custom** if you only want to install selected components. If you selected Custom, you'll be asked which Pentaho applications you want to install. For a server installation, uncheck all options except **BA Server** and **Data Integration Server**. If you have a Pentaho Dashboards Enterprise Edition or Pentaho Analysis Enterprise Edition license key, select the checkboxes for the **Dashboard Designer** and **Pentaho Analyzer** options, respectively.

If you do not have the requisite support entitlements, the Dashboard Designer and Pentaho Analyzer plugins will not work, and they will change your Pentaho User Console interface permanently. There is no direct harm in installing these plugins if you do not have support entitlements for them; however, you will have to ensure that your users are properly trained to avoid the disabled functions in the Pentaho User Console. If necessary, it is possible to install Dashboard Designer and Pentaho Analyzer later by using archive packages.

 **Note:** If you install Pentaho Analyzer, you must also install Dashboard Designer due to a software dependency.

5. If you selected Custom, then you'll be asked if you would like to install the Pentaho sample data. Select **No** if this is a production installation.
The sample data is useful for testing and evaluating Pentaho Business Analytics, but tends to get in the way in a production environment.
6. Next, you'll be asked to choose a directory to install to. Feel free to select a new path, but for documentation continuity and support purposes, you should leave the actual directory name alone. The default directory is `C:\Program Files\pentaho\`.
You cannot install into a directory that already exists.
7. In the next screen, type in a master password for the MySQL database, Enterprise Console admin user, and the BA Server publish function.
The Pentaho Business Analytics installer provides a MySQL database to store your reports and analysis views. The root password is for the internal database root user, not the global system root (administrator) user. This is the account that has total control over all MySQL databases. The admin password is for the Pentaho Enterprise Console (username **admin**). The publish password is used whenever you publish content from a workstation (via Pentaho design tools) to the BA Server.
8. Optional: If any of the default Pentaho BA and DI Server ports (**8088, 8080, 8012, 9092, 9080, 8443, 8143, and 3306**) are not available on your system, the default numbers will increment by one until an available port is found.
9. If you chose a custom installation, a summary screen will show you an overview of which Pentaho Business Analytics components you've chosen to install, and the ports that all of the necessary services will run on. Click **Next** to leave this screen, then **Next** again to commence installation. If you chose the default installation, you only have to click **Next** once here.

Once the installation wizard is complete, the BA Server and DI Server should be up and running with default parameters. You have the option of viewing an installation summary and starting the Pentaho User Console during the last step of the installation process. If you choose the Pentaho User Console option, your default Web browser will open to the Pentaho User Console login screen. A PDF copy of the *Getting Started With Pentaho* evaluation document will also appear once you click the **Finish** button on the last screen of the installer.



Note: Terminal windows may remain open after installation. Closing them will terminate the BA Server and DI Server processes for this session.



Note: The BA Server and DI Server are now installed as system services in Windows, meaning they will start and stop when Windows starts up and shuts down. The Pentaho Enterprise Console must be manually run from the Start menu, however.

Installing on Linux

Because of Linux' more modular and secure design, the installation instructions are different than for Windows.

The licensing technology in the BA Server requires that you take all of the steps below to ensure that all system users have access to content and tools through the Pentaho User Console. If you used the graphical installation utility to evaluate the Pentaho Business Analytics on Linux before you purchased a subscription, you did not have to establish a new user account or worry much about licensing. However, the procedure is more involved on a production server, where more than one user will be accessing the Pentaho User Console or managing BA Server licenses.



Note: Pentaho strongly discourages administrators from installing to the `/opt/` directory due to its complicated permissions requirements and general isolation from the rest of the system.

Using the Linux Installation Utility

These instructions are for Linux users only. Windows users should refer to the Windows installation instructions instead.



Important: If you do not have an X server installed, you can run the installation utility in text mode by invoking the **--mode text** switch. If you like, you can also perform the installation on a Linux workstation, then transfer over the `/pentaho/` and `~/ .pentaho/` directories to your server after installation.



Note: The installation utility's graphical mode defaults to the GTK graphics toolkit. If you do not have the requisite GTK libraries on your system, you can run the installer with the **--mode xwindow** switch to use OpenMotif instead.

Step-by-step instructions for using the installer are below. You may need to adjust the instructions for your specific situation.

1. Open a terminal window.

2. If it is not already there, copy the installation utility to the **pentaho** home directory.

```
cp /home/rwilco/Desktop/pentaho-bi-suite-4.5.0-GA-i386.bin /home/pentaho/
```

3. Switch to the **pentaho** user account.

```
su pentaho -
```

4. Set execute permissions on the installation utility.

```
chmod +x ./pentaho-bi-suite-4.5.0-GA-i386.bin
```

5. Run the installation utility.

```
/home/rwilco/Desktop/pentaho-bi-suite-4.5.0-GA-i386.bin
```

6. When the installation utility starts, you'll see a Pentaho splash screen. Click Next.

7. Accept the license agreement to continue.

8. When prompted for which setup type you'd like to perform, select **Default** if you want to install the entire Pentaho Business Analytics on one machine, or **Custom** if you only want to install selected components. If you selected Custom, you'll be asked which Pentaho applications you want to install. For a server installation, uncheck all options except **BA Server** and **Data Integration Server**. If you have a Pentaho Dashboards Enterprise Edition or Pentaho Analysis Enterprise Edition license key, select the checkboxes for the **Dashboard Designer** and **Pentaho Analyzer** options, respectively.

If you do not have the requisite support entitlements, the Dashboard Designer and Pentaho Analyzer plugins will not work, and they will change your Pentaho User Console interface permanently. There is no direct harm in installing these plugins if you do not have support entitlements for them; however, you will have to ensure that your users are properly trained to avoid the disabled functions in the Pentaho User Console. If necessary, it is possible to install Dashboard Designer and Pentaho Analyzer later by using archive packages.



Note: If you install Pentaho Analyzer, you must also install Dashboard Designer due to a software dependency.

9. If you selected Custom, then you'll be asked if you would like to install the Pentaho sample data. Select **No** if this is a production installation.

The sample data is useful for testing and evaluating Pentaho Business Analytics, but tends to get in the way in a production environment.

10. Next, you'll be asked to choose a directory to install to. Feel free to select a new path, but for documentation continuity and support purposes, you should leave the actual directory name alone. The default directory is `~/pentaho/`

You cannot install into a directory that already exists.

11. In the next screen, type in a master password for the MySQL database, Enterprise Console admin user, and the BA Server publish function.

The Pentaho Business Analytics installer provides a MySQL database to store your reports and analysis views. The root password is for the internal database root user, not the global system root (administrator) user. This is the account that has total control over all MySQL databases. The admin password is for the Pentaho Enterprise Console (username **admin**). The publish password is used whenever you publish content from a workstation (via Pentaho design tools) to the BA Server.

12. Optional: If any of the default Pentaho BA and DI Server ports (**8088, 8080, 8012, 9092, 9080, 8443, 8143, and 3306**) are not available on your system, the default numbers will increment by one until an available port is found.

13. If you chose a custom installation, a summary screen will show you an overview of which of the Pentaho Business Analytics components you've chosen to install, and the ports that all of the necessary services will run on. Click **Next** to leave this screen, then **Next** again to commence installation. If you chose the default installation, you only have to click **Next** once here.

Once the installation wizard is complete, the BA Server and DI Server should be up and running with default parameters. You have the option of viewing an installation summary and starting the Pentaho User Console during the last step of the installation process. If you choose to go to the Pentaho User Console, your default Web browser will open and display the BA Server login screen.

Starting the Servers At Boot Time On Linux

This procedure assumes that you will be running your BA Server, DI Server, and Pentaho Enterprise Console server under the **pentaho** local user account, as recommended by Pentaho and explained earlier in this guide. If you are using a different account to start these services, use it in place of the pentaho user account in the script below.

You can start and stop the BA and DI Servers at any time by running the **start-pentaho.sh** and **stop-pentaho.sh** scripts in the `/pentaho/server/biserver-ee/` and `/pentaho/server/data-integration-server/` directories, respectively, or you can start and stop the entire stack -- MySQL, Tomcat, DI Server, and the Pentaho Enterprise Console -- with the provided `ctlscript.sh` script in the **/pentaho/** directory. To start the Tomcat server automatically at boot time, and stop automatically during shutdown, follow the below procedure.

1. With root permissions, create a file in `/etc/init.d/` called **pentaho**.
2. Using a text editor, copy the following content into the new pentaho script, changing **mysql** to the name of the init script for your database if it is running on the remote machine, or remove **mysql** entirely if you are using a remote database. Secondly, you must adjust the paths to the BA Server, DI Server, and Pentaho Enterprise Console scripts to match your situation.

```
#!/bin/sh -e
### BEGIN INIT INFO
# Provides: pentaho
# Required-Start: networking
# Required-Stop:
# Default-Start: 2 3 4 5
# Default-Stop: 0 1 6
# Description: Pentaho BA Server
### END INIT INFO

case "$1" in
"start")
su - pentaho -c "/home/pentaho/pentaho/mysql/scripts/ctl.sh start"
su - pentaho -c "/home/pentaho/pentaho/server/biserver-ee/start-pentaho.sh"
su - pentaho -c "/home/pentaho/pentaho/server/data-integration-server/start-pentaho.sh"
su - pentaho -c "cd /home/pentaho/pentaho/server/enterprise-console && ./start-pec.sh"
;;
"stop")
su - pentaho -c "/home/pentaho/pentaho/mysql/scripts/ctl.sh stop"
su - pentaho -c "/home/pentaho/pentaho/server/biserver-ee/stop-pentaho.sh"
su - pentaho -c "/home/pentaho/pentaho/server/data-integration-server/stop-pentaho.sh"
su - pentaho -c "cd /home/pentaho/pentaho/server/enterprise-console && ./stop-pec.sh"
;;
*)
echo "Usage: $0 { start | stop }"
;;
esac
exit 0
```

3. Save the file and close the text editor.
4. Make the init script executable.

```
chmod +x /etc/init.d/pentaho
```

5. Add the pentaho init script to the standard runlevels so that it will run when the system starts, and stop when the system is shut down or rebooted, by using the `update-rc.d` command.

This command may not exist on your computer if it is not Debian-based. If that is the case, consult your distribution documentation or contact your distribution's support department to determine how to add init scripts to the default runlevels.

```
update-rc.d pentaho defaults
```

The Pentaho BA Server will now start at boot time, and shut down when the system stops or restarts.

Using the Mac Installation Utility

These instructions are for OS X users only. Windows and Linux users have separate instructions.

Step-by-step instructions for using the installer are below. You may need to adjust the instructions for your specific situation.

1. Double-click the **pentaho-bi-suite-4.5.0-GA-x64.app** file.
2. When the installation utility starts, you'll see a Pentaho splash screen. Click **Next**.
3. Accept the license agreement to continue.
4. When prompted for which setup type you'd like to perform, select **Default** if you want to install the entire Pentaho Business Analytics on one machine, or **Custom** if you only want to install selected components. If you selected Custom, you'll be asked which Pentaho applications you want to install. For a server installation, uncheck all options except **BA Server** and **Data Integration Server**. If you have a Pentaho Dashboards Enterprise Edition or Pentaho Analysis Enterprise Edition license key, select the checkboxes for the **Dashboard Designer** and **Pentaho Analyzer** options, respectively.

If you do not have the requisite support entitlements, the Dashboard Designer and Pentaho Analyzer plugins will not work, and they will change your Pentaho User Console interface permanently. There is no direct harm in installing these plugins if you do not have support entitlements for them; however, you will have to ensure that your users are properly trained to avoid the disabled functions in the Pentaho User Console. If necessary, it is possible to install Dashboard Designer and Pentaho Analyzer later by using archive packages.
5. If you selected Custom, then you'll be asked if you would like to install the Pentaho sample data. Select **No** if this is a production installation.

The sample data is useful for testing and evaluating Pentaho Business Analytics, but tends to get in the way in a production environment.
6. Next, you'll be asked to choose a directory to install to. Feel free to select a new path, but for documentation continuity and support purposes, you should leave the actual directory name alone. The default directory is `/Applications/pentaho/`

You cannot install into a directory that already exists.
7. In the next screen, type in a master password for the MySQL database, Enterprise Console admin user, and the BA Server publish function.

Pentaho Business Analytics installer provides a MySQL database to store your reports and analysis views. The root password is for the internal database root user, not the global system root (administrator) user. This is the account that has total control over all MySQL databases. The admin password is for the Pentaho Enterprise Console (username **admin**). The publish password is used whenever you publish content from a workstation (via Pentaho design tools) to the BA Server.
8. Optional: If any of the default Pentaho BA and DI Server ports (**8088, 8080, 8012, 9092, 9080, 8443, 8143, and 3306**) are not available on your system, the default numbers will increment by one until an available port is found.
9. If you chose a custom installation, a summary screen will show you an overview of which Pentaho Business Analytics components you've chosen to install, and the ports that all of the necessary services will run on. Click **Next** to leave this screen, then **Next** again to commence installation. If you chose the default installation, you only have to click **Next** once here.

Once the installation wizard is complete, the BA Server and DI Server should be up and running with default parameters. You have the option of viewing an installation summary and starting the Pentaho User Console during the last step of the installation process. If you choose to go to the Pentaho User Console, your default Web browser will open and display the BA Server login screen.

Installing the Analysis Enterprise Edition Plugin

Follow the instructions below to install the Pentaho Analysis Enterprise Edition package, which contains Analysis engine enhancements for large ROLAP deployments.



Note: This procedure does not cover Pentaho Analyzer installation.



Note: If you are performing a manual WAR build and deployment, and you want to slipstream the Pentaho Analysis Enterprise Edition JARs into the WAR pre-build, you can substitute `/biserver-manual-ee/build-resources/custom-pentaho-webapp/WEB-INF/` for `/WEB-INF/` references below.

1. If you have not already done so, retrieve the **pentaho-analysis-ee-3.4.0-GA** package from the Pentaho Customer Support Portal (login credentials were emailed to you with your Welcome Kit).

2. Unpack the archive to a temporary location.
3. If it is currently running, shut down the BA Server.
4. Copy only the following JARs from the `/pentaho-analysis-ee/lib/` directory to the `/WEB-INF/lib/` directory inside of the deployed pentaho.war:
 - infinispan-core-4.3.FINAL
 - jboss-transaction-api-1.0.1.GA
 - jcip-annotations-1.0
 - jgroups-2.12.0.CR5
 - marshalling-api-1.2.3.GA
 - memcached-0.0.1-PENTAHO
 - pentaho-analysis-ee-3.4.0-GA-obf
 - river-1.2.3.GA
5. Copy all of the configuration files from `/pentaho-analysis-ee/config/` to the `/WEB-INF/classes/` directory inside of your deployed pentaho.war.
6. Remove the temporary **pentaho-analysis-ee** directory.

Pentaho Analysis Enterprise Edition is now installed with the default Infinispan configuration.

If you need to switch from Infinispan to Memcached, continue to the next section.

Switching to Memcached

In order to complete this procedure, you must have your own pre-configured Memcached instance. You should have also installed the Analysis Enterprise Edition package to your BA Server or standalone Mondrian engine.

If you already use the Memcached cache framework in your organization and would like to hook it up to the Pentaho Analysis ROLAP engine, follow the directions below to switch from the default Infinispan cache framework configuration.



Caution: Pentaho and Mondrian developers recommend against using Memcached. You are almost certain to have better performance with Infinispan.

1. If the BA Server or standalone Mondrian engine are running, shut them down now.
2. If you performed a default install of the Pentaho Analysis Enterprise Edition package, then you should have all of the required JARs installed to the BA or Mondrian server. If you aren't sure, verify now that the following JARs are present in the `/WEB-INF/lib/` directory inside of your deployed pentaho.war or Mondrian engine:
 - pentaho-analysis-ee
 - commons-lang
 - commons-io
 - commons-codec
 - pentaho-ee-dsc-core
 - memcached

3. Edit the **pentaho-analysis-config.xml** in the `/WEB-INF/classes/` directory inside the deployed pentaho.war or Mondrian engine, and change the value of **SEGMENT_CACHE_IMPL** to match the class name referenced below:

```
<entry key="SEGMENT_CACHE_IMPL">com.pentaho.analysis.segmentcache.impl.memcached.MemcachedSegmentCache</entry>
```

4. Edit the **memcached-config.xml** in the `/WEB-INF/classes/` directory inside the deployed pentaho.war or Mondrian engine, and change the values of **SALT**, **SERVERS**, and **WEIGHT** to match your preference:

Refer to [Memcached Configuration Options](#) on page 18 for more information on these settings.

```
<entry key="SALT">YOUR SECRET SALT VALUE HERE</entry>
```


```
<entry key="SERVERS">192.168.0.1:1642,192.168.0.2:1642</entry>
```

```
<entry key="WEIGHTS">1,1</entry>
```

Your Pentaho Analysis Enterprise Edition instance is now configured to use Memcached for ROLAP segment caching.

Memcached Configuration Options


These properties control Memcached settings, and are set in the **memcached-config.xml** file in the `/WEB-INF/classes/` directory inside of your deployed pentaho.war or Mondrian engine.

 **Note:** This is not a comprehensive list of the potential Memcached settings; the options explained below are the ones most critical to Memcached configuration for Pentaho Analysis. You must research further Memcached options on your own.

| Property | Purpose |
|----------|---|
| SERVERS | A comma-separated list of servers and port numbers representing the Memcached nodes usable by the plugin. |
| WEIGHTS | A comma-separated list of numbers representing the relative caching capacity of the servers defined in the SERVERS property. There must be exactly as many values of WEIGHTS as there are values of SERVERS. As an example, if the first server has a capacity of 128 megabytes, and the second has a capacity of 256 megabytes, the correct values for the WEIGHTS property should be "1,2", indicating that the first server has a relative size of half of the second one. |
| SALT | A secret key prefix to be used when saving and loading segment data from the Memcached nodes. This property must be the same for all Mondrian nodes that share their caches. If the SALT value is different from one node to the next, the nodes will not be able to share their cache data. |

Adding Linux and OS X Support for Printing Analyzer Geo Maps

There is an experimental function in Analyzer that enables you to print Geo Map visualizations. Follow the directions below to enable support on Linux and OS X. Windows configuration is covered in [Adding Windows Support for Printing Analyzer Geo Maps](#) on page 19.

 **Note:** Pentaho requires a specific version of **wkhtmltoimage** in order for this print function to work correctly. Even if you have wkhtmltoimage installed on your machine, install the Pentaho-supplied version as explained below. It will be explicitly called by Analyzer, and will not interfere with your existing wkhtmltoimage instance.

 **Note:** If you used the Business Analytics graphical installer, **skip all steps except the last two.**

1. Navigate to the **wkhtmltoimage** directory in your Pentaho installation. For archive installations, this is `/pentaho/biserver-ee/third-party-tools/wkhtmltoimage/`, and for manual deployments it is `/biserver-manual-ee/build-resources/third-party-tools/wkhtmltoimage/`.
2. For OS X, unpack the **wkhtmltoimage_mac.tar.bz2** package; for 32-bit Linux, unpack the **wkhtmltoimage_linux_i386.tar.bz2** package; for 64-bit Linux, unpack the **wkhtmltoimage_linux_amd64.tar.bz2** package.

There is only one file in this archive: a **wkhtmltoimage** executable.

3. Edit the `/pentaho-solutions/system/pentaho.xml` file and set the value of **<html-to-image-tool>** to the full path to the **wkhtmltoimage** executable that you just unpacked.

```
<html-to-image-tool>/home/pentaho/pentaho/server/biserver-ee/wkhtmltoimage/wkhtmltoimage</html-to-image-tool>
```

4. Save and close the file, then edit the `/pentaho-solutions/system/analyzer/settings.xml` file and uncomment the following line:

```
<!--open_layers>geomapexport</open_layers-->
```

5. Save and close the settings.xml file.

You have enabled the experimental print feature for Analyzer Geo Map visualizations.

Adding Windows Support for Printing Analyzer Geo Maps

There is an experimental function in Analyzer that enables you to print Geo Map visualizations. Follow the below directions to enable support on Windows. Linux and OS X configuration are covered in [Adding Linux and OS X Support for Printing Analyzer Geo Maps](#) on page 18.



Note: Pentaho requires a specific version of **wkhtmltoimage** in order for this print function to work correctly. Even if you have wkhtmltoimage installed on your machine, install the Pentaho-supplied version as explained below. It will be explicitly called by Analyzer, and will not interfere with your existing wkhtmltoimage instance.



Note: If you used the Business Analytics graphical installer, **skip all steps except the last two.**

1. Navigate to the **wkhtmltoimage** directory in your Pentaho installation. For archive installations, this is `\pentaho\biserver-ee\third-party-tools\wkhtmltoimage\`, and for manual deployments it is `\biserver-manual-ee\build-resources\third-party-tools\wkhtmltoimage\`.
2. Run the **wkhtmltoimage_windows_installer.exe** executable.
3. Accept the license agreement to continue.
4. Uncheck the **wkhtmltopdf** option, then click **Next**.
5. For the **Destination folder**, type in or navigate to the path that you found this utility in, then click **Install**. For instance: **C:\pentaho\biserver-ee\third-party-tools\wkhtmltoimage**.
6. When the installation is complete, click **Close**, then edit the `\pentaho-solutions\system\pentaho.xml` file and set the value of **<html-to-image-tool>** to the full path to the **wkhtmltoimage** executable that you specified in the installer, including the executable name of the package, which is **wkhtmltoimage**.

```
<html-to-image-tool>C:\pentaho\biserver-ee\third-party-tools\wkhtmltoimage\wkhtmltoimage.exe</html-to-image-tool>
```
7. Close that file, then edit the `\pentaho-solutions\system\analyzer\settings.xml` file and uncomment the following line:

```
<!--open_layers>geomapexport</open_layers-->
```
8. Save and close the settings.xml file.

You have enabled the experimental print feature for Analyzer Geo Map visualizations.

Post-Install Configuration

After you've successfully installed the BA Server on your server, you must set up your configuration information and other details. All of this is done through the Pentaho Enterprise Console.

1. Open a Web browser and navigate to **http://localhost:8088** (change **localhost** to the IP address, hostname, or domain name of your BI Platform).
2. Log in as **admin** with the password you set during installation.
3. Click the **+** (plus) button in the upper right corner of the Subscriptions section.

An **Install License** dialogue will appear.



Note: If you previously installed Pentaho Business Analytics with an evaluation license, that license may still be active. If so, the Pentaho Enterprise Console may skip the configuration screen and go straight to the overview page. If that happens, click the wrench icon in the upper right corner of the screen to get back to the configuration options.

4. Click **Browse**, then navigate to the location you saved your LIC files to, click on one of the LIC files, then click **Open**.
LIC files for each of your supported Pentaho products were emailed to you along with your Pentaho Welcome Kit. If you did not receive this email, or if you have lost these files, contact your Pentaho support representative. If you do not yet have a support representative, contact the Pentaho salesperson you were working with.
5. Click **OK**.

The Setup screen will change according to the LIC file you installed. **Repeat the LIC file installation process for each support entitlement you have purchased.**

6. In the **Solution Directory** field, enter `/pentaho/server/biserver-ee/pentaho-solutions/`, or whatever the path to your pentaho-solutions directory is.
7. In the **Backup Directory** field, type in the location that you'd like to save Pentaho Enterprise Console backup data to.
This can be any local directory that your application server has permissions to write to. You cannot, however, use relative paths in this or any other configuration field in this screen -- **all paths must be absolute**.
8. In the **Pentaho Web-App Path** field, enter `/tomcat/webapps/pentaho/`, or whatever the path to the unpacked pentaho.war directory is for your application server.
9. In the **Platform Administrator User Name** field, type in **admin**, or if you already have Pentaho User Console accounts established, type in the account name that you will use to manage reports and schedules.
This user account does not have to exist yet, and you can change this value later.
10. Click **OK**.
The rest of the settings in this screen do not need to change right now.
11. Click **Configuration** in the menu on the left side of Pentaho Enterprise Console.
12. Click the **Web Settings** tab at the top of the screen.
13. Change the **Fully Qualified Server URL** setting to match your server's hostname, domain name, or IP address. Do not change the directory or port number.

If you need to change the port number, consult the *Pentaho Business Analytics Administrator's Guide*.

Your Pentaho BA Server now has a minimal configuration. If you need to return to this screen, click on the wrench/screwdriver icon in the upper right corner of the screen.

Your administration work is only beginning; you should now consult the *Pentaho Business Analytics Administrator's Guide* to learn your way around the Pentaho Enterprise Console.

Changing the Default Port Numbers

The Pentaho-provided Tomcat instance is preconfigured to run on port **8080**, and the Pentaho Enterprise Console is configured for port **8088**. If you want to change these port numbers, follow the below procedure.

1. Navigate to the `/pentaho/server/biserver-ee/tomcat/conf/` directory
2. Edit the **server.xml** file found there, and search for **Define a non-SSL HTTP/1.1 Connector**. Change the port number in the **Connector port** element below that from **8080** to your preferred port number.

```
<!-- Define a non-SSL HTTP/1.1 Connector on port 8080 -->
<Connector port="8080" maxHttpHeaderSize="8192"
    maxThreads="150" minSpareThreads="25" maxSpareThreads="75"
    enableLookups="false" redirectPort="8443" acceptCount="100"
    connectionTimeout="20000" disableUploadTimeout="true" />
```

3. Save and close the file, then navigate to the `/pentaho/server/biserver-ee/tomcat/webapps/pentaho/WEB-INF/` directory and edit the **web.xml** file found there.
4. Change the **fully-qualified-server-url** entry to match the new port number you specified in server.xml.

```
<context-param>
  <param-name>fully-qualified-server-url</param-name>
  <param-value>http://localhost:8080/pentaho/</param-value>
</context-param>
```

5. Save and close the file, then navigate to the `/pentaho/server/enterprise-console/resource/config/` and edit the **console.properties** file found there.
6. Change the **console.start.port.number** and **console.stop.port.number** values to match the port numbers you want to run Enterprise Console on.

```
console.start.port.number=8088
console.stop.port.number=8033
```

Workstation Installation Procedure

You must disable any anti-spyware software before installing Pentaho Business Analytics. Some types of software firewalls and anti-virus scanners may also block the Pentaho Business Analytics or prevent it from operating normally.

The Pentaho Business Analytics client tools are:

- Report Designer
- Metadata Editor
- Schema Workbench
- Design Studio
- Data Integration
- Aggregation Designer

These programs are easily installed on Windows-, OS X- and Linux-based workstations by running the Pentaho Business Analytics graphical installer.

1. Run the installation utility as you would any other program - double-click it.
On Linux systems, you may have to set execute permissions on the installer before trying to run it.
2. When the installation utility starts, you'll see a Pentaho splash screen. Click **Forward**.
3. Accept the license agreement to continue.
4. When prompted for which installation scenario you want, select **Custom** and click **Next**.
5. Un-check the options for **BA Server**, **Analyzer**, **Dashboard Designer**, **Pentaho Enterprise Console**, and **Data Integration Server**, and ensure that all of the Pentaho design tools you want to install are checked.
6. A summary screen will show you an overview of which Pentaho Business Analytics components you've chosen to install. Click **Forward** to leave this screen, then **Forward** again to commence installation.

The selected client tools should now be installed and ready to use. On Windows, they'll be available through the Start menu; on Linux systems, they'll be available through the command line, or you can create your own shortcuts on your desktop or in the GNOME or KDE panels. The default installation directory is `C:\Program Files\pentaho\design-tools\` on Windows, `/Applications/pentaho/design-tools/` on OS X, and `~/pentaho/design-tools/` on Linux.

Testing and Using Your Server

To verify that the BA Server is installed and running, open a Web browser on a workstation and navigate to **http://example.com:8080/pentaho/** (substituting **example.com** for your BA Server's hostname, IP address, or domain name). You should see a Web page similar to the below picture:



When your system is properly configured, log in with your administrator account, then verify that you can do the following, assuming your data has been prepared for reporting and analysis:

- Create a new analysis view.
- Create a new ad hoc report.
- If you are a Dashboards Enterprise Edition customer, create a new dashboard with the Dashboard Designer plugin.
- If you are a Pentaho Analysis Enterprise Edition customer, create a new analysis report with the Pentaho Analyzer plugin.
- In Pentaho Data Integration, create or connect to an enterprise repository and a data source.
- Schedule a report to run at a regular interval.
- Using Pentaho Report Designer, publish a report to the BA Server.

Preparing for Production

The default condition of the BA Server is designed to support quick and easy evaluation by new customers. Once you move from evaluation to production, you may want to remove some of the evaluation-specific features in the BA Server. The instructions in this section explain how to remove them.

Removing Pentaho Sample Data and Solutions

By default, Pentaho provides a sample data source and a solution directory filled with example content. These samples are provided for evaluation and testing. Once you are ready to move from an evaluation or testing scenario to development or production, you should remove the samples so that they do not get in the way of your BI content. Follow the instructions below to completely remove the Pentaho sample data and solutions.

1. Stop the BA Server.
2. If they exist, delete the `/pentaho/server/biserver-ee/pentaho-solutions/steel-wheels/` and `/pentaho/server/biserver-ee/pentaho-solutions/bi-developers/` directories.
These directories contain sample content for CDF and BA Server plugins. They are not present in typical manual deployment scenarios.
3. Edit the `/pentaho/WEB-INF/web.xml` file inside of the deployed `pentaho.war`.
As laid down by the Pentaho graphical installer and archive packages, this path should be `/pentaho/server/biserver-ee/tomcat/webapps/pentaho/WEB-INF/web.xml`. If you performed a manual WAR build and deployment, then you must adjust the path to fit your configuration.
4. Remove the sample servlets by commenting them out or removing them from the file:

```
<!-- [BEGIN SAMPLE SERVLETS] -->
<servlet>
  <servlet-name>UpdateSampleEmails</servlet-name>
  <jsp-file>/jsp/UpdateSampleEmails.jsp</jsp-file>
</servlet>

<servlet>
  <servlet-name>Widgets</servlet-name>
  <jsp-file>/jsp/Widgets.jsp</jsp-file>
</servlet>

<servlet>
  <servlet-name>SampleDashboard</servlet-name>
  <jsp-file>/jsp/SampleDashboard.jsp</jsp-file>
</servlet>

<servlet>
  <servlet-name>ChartSamplesDashboard</servlet-name>
  <jsp-file>/jsp/ChartSamplesDashboard.jsp</jsp-file>
</servlet>

<servlet>
  <servlet-name>SampleDrill</servlet-name>
  <jsp-file>/jsp/SampleDrill.jsp</jsp-file>
</servlet>

<servlet>
  <servlet-name>SWDashboard</servlet-name>
  <jsp-file>/jsp/SWDashboard.jsp</jsp-file>
</servlet>

<servlet>
  <servlet-name>Map</servlet-name>
  <jsp-file>/jsp/Map.jsp</jsp-file>
</servlet>

<servlet>
  <servlet-name>SampleFlashDashboard</servlet-name>
  <jsp-file>/jsp/SampleFlashDashboard.jsp</jsp-file>
```

```

</servlet>
<!-- [END SAMPLE SERVLETS] -->

```

5. Remove the sample servlet mappings in the same fashion:

```

<!-- [BEGIN SAMPLE SERVLET MAPPINGS] -->
<servlet-mapping>
  <servlet-name>UpdateSampleEmails</servlet-name>
  <url-pattern>/UpdateSampleEmails</url-pattern>
</servlet-mapping>

<servlet-mapping>
  <servlet-name>Widgets</servlet-name>
  <url-pattern>/Widgets</url-pattern>
</servlet-mapping>

<servlet-mapping>
  <servlet-name>SampleDashboard</servlet-name>
  <url-pattern>/SampleDashboard</url-pattern>
</servlet-mapping>

<servlet-mapping>
  <servlet-name>ChartSamplesDashboard</servlet-name>
  <url-pattern>/ChartSamplesDashboard</url-pattern>
</servlet-mapping>

<servlet-mapping>
  <servlet-name>SampleDrill</servlet-name>
  <url-pattern>/SampleDrill</url-pattern>
</servlet-mapping>

<servlet-mapping>
  <servlet-name>SWDashboard</servlet-name>
  <url-pattern>/SWDashboard</url-pattern>
</servlet-mapping>

<servlet-mapping>
  <servlet-name>Map</servlet-name>
  <url-pattern>/Map</url-pattern>
</servlet-mapping>

<servlet-mapping>
  <servlet-name>SampleFlashDashboard</servlet-name>
  <url-pattern>/SampleFlashDashboard</url-pattern>
</servlet-mapping>
<!-- [END SAMPLE SERVLET MAPPINGS] -->

```

6. Remove the **SampleDataStartupListener**:

```

<listener>
  <listener-class>org.pentaho.platform.web.http.context.HsqldbStartupListener</
listener-class>
</listener>

```


7. Remove the **hsqldb-databases** section:

```

<!-- [BEGIN HSQLDB DATABASES] -->
<context-param>
  <param-name>hsqldb-databases</param-name>
  <param-value>sampladata@../../data/hsqldb/sampladata</param-value>
</context-param>
<!-- [END HSQLDB DATABASES] -->

```

8. Remove the **SystemStatusFilter** filter:

 **Note:** This is not part of the Pentaho samples; it provides error status messages that are only useful for development and testing purposes, and should be removed from a production system.

```

<filter>
  <filter-name>SystemStatusFilter</filter-name>
  <filter-class>com.pentaho.ui.servlet.SystemStatusFilter</filter-class>
  <init-param>
    <param-name>initFailurePage</param-name>

```



```
<param-value>InitFailure</param-value>
<description>This page is displayed if the PentahoSystem fails to properly
initialize.</description>
</init-param>
</filter>
```

9. Remove the filter mapping for the `SystemStatusFilter`:

```
<filter-mapping>
  <filter-name>SystemStatusFilter</filter-name>
  <url-pattern>/*</url-pattern>
</filter-mapping>
```

10. Save and close the `web.xml` file.

11. Delete the `/pentaho/server/biserver-ee/data/` directory.

This directory contains a sample database, control scripts for that database and the environment settings it needs to run, and SQL scripts to initialize a new Pentaho solution repository.

Your BA Server instance is now cleaned of samples and development/testing pieces, and is streamlined for production.

Switching to a Production Login Screen

The default Pentaho User Console login screen contains information and instructions for evaluators. Pentaho allows this extra information to be hidden via configuration; follow the directions below to hide the extra information.

1. Shut down the BA Server and Enterprise Console if they are currently running.
2. Open a terminal or file browser window and navigate to the `/pentaho-solutions/system/` directory.
If you installed via the archive package or the graphical installer, the full path is `/pentaho/server/biserver-ee/pentaho-solutions/system/`.
3. Edit the **`pentaho.xml`** file.
4. Find the **`login-show-sample-users-hint`** node and change its value to **`false`**.
5. Start the BA Server and Pentaho Enterprise Console.

You now have a login screen that has been scrubbed of evaluation content.

Uninstalling Pentaho Business Analytics

Uninstalling the BA Server and the client tools is easy -- simply shut down all Pentaho services and programs, then run the **uninstall** utility in the `/pentaho/` directory. For Windows users, this script can also be accessed through the Pentaho folder in the Windows Start menu.

Master Service Control Scripts From the Graphical Installer


If you installed Pentaho Business Analytics on a single machine through Pentaho's graphical installation utility, then there is a global service control script in the top-level directory that you installed to: **ctlscript** (.sh on Linux, .bat on Windows). This will start the BA Server, DI Server, Enterprise Console, MySQL solution database, and hsqldb sample database. ctlscript takes the following arguments:

- start
- stop
- restart
- status
- help

If you installed the Data Integration (DI) Server through the PDI graphical installation utility, you will have a ctlscript that will control the DI Server, Enterprise Console, and hsqldb sample database.

Appendix: Default Pentaho Business Analytics Port Numbers

The table below lists all of the important Pentaho Business Analytics port numbers and the services they correspond to. If you manually changed any port numbers, or if the default numbers were not available when you used the graphical installer, then these numbers will be different. The graphical installer increments port numbers by 1 until it finds free ports; typically it does not have to go beyond one increment if it detects an occupied port.

 **Note:** The numbers below represent a complete Pentaho Business Analytics installation. If you only install the BA Server or the DI Server, some port numbers may not apply.

| Port number | Service |
|-------------|----------------------|
| 3306 | MySQL server |
| 8080 | BA Server (Tomcat) |
| 8012 | BA Server shutdown |
| 8088 | Enterprise Console |
| 9080 | DI Server |
| 9092 | Embedded H2 database |

This section contains known problems and solutions relating to the procedures covered in this guide.

Evaluation Licenses are Not Granted

If you see a message in the graphical installation utility's error log that says, **Evaluation licenses were not granted for the following products**, this means that you've installed this version of Pentaho Business Analytics (or some piece of it) in the past, and one or more evaluation licenses have already been generated and installed. An evaluation license expires 30 days after it is generated; once expired, it cannot be reactivated. The only way to use Pentaho Business Analytics's full functionality is to install a new, active license that overwrites the old one.

In some cases, you may have delayed or extended your Pentaho evaluation beyond the automatic license's term. If you need more time, contact your Pentaho sales representative or pre-sales support engineer.

Compatibility Matrix: List of Supported Products

32-bit Operating Systems

Both servers and workstations are covered in the table below; it's assumed that server software and engines will run on server machines, and design tools will run on workstations. 32-bit operating systems in production environments are becoming more rare. This list will grow shorter with time.

| | BA Enterprise Console | Data Server | Reporting Engine | Analysis Engine | Data Integration Engine | Design Studio | Report Designer | Data Integration | Metadata Editor | Schema Workbench | Aggregation Designer |
|---|-----------------------------|----------------|---------------------|--------------------|-------------------------------|------------------|--------------------|---------------------|--------------------|---------------------|-------------------------|
| Windows XP | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Windows 7 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Windows 2008 Server | Y | Y | Y | Y | Y | N | N | N | N | N | N |
| SUSE Linux Enterprise Desktop/Server 10 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Red Hat Enterprise Linux 5 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Ubuntu Linux 10.04 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Solaris 10 | Y | Y | Y | Y | Y | Y | Y | Y | Y | N | N |

64-bit Operating Systems

Both servers and workstations are covered in the table below; it's assumed that server software and engines will run on server machines, and design tools will run on workstations. All modern operating systems have 64-bit versions, and will become the standard in the future. This list will grow longer with time.

| | BA Enterprise Console | Data Server | Reporting Engine | Analysis Engine | Data Integration Engine | Design Studio | Report Designer | Data Integration | Metadata Editor | Schema Workbench | Aggregation Designer |
|---|-----------------------------|----------------|---------------------|--------------------|-------------------------------|------------------|--------------------|---------------------|--------------------|---------------------|-------------------------|
| Windows 7 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Windows 2008 Server | Y | Y | Y | Y | Y | N | N | N | N | N | N |
| Mac OS X | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| SUSE Linux Enterprise Desktop/Server 10 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Red Hat Enterprise Linux 5 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |

| | BA Server/Enterprise Console | Data Integration Engine | Reporting Engine | Analysis Engine | Data Integration Engine | Design Studio | Report Designer | Data Integration Engine | Metadata Editor | Schema Workbench | Aggregation Designer |
|--------------------|------------------------------|-------------------------|------------------|-----------------|-------------------------|---------------|-----------------|-------------------------|-----------------|------------------|----------------------|
| Ubuntu Linux 10.04 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |


Application Server

This refers to the Java application server used by Pentaho server applications and engines.

| | BA Server/Enterprise Console | Data Integration Server | Reporting Engine | Analysis Engine | Data Integration Engine |
|--------------|------------------------------|-------------------------|------------------|-----------------|-------------------------|
| JBoss 5.1.x | Y | N | Y | Y | Y |
| Tomcat 6.0.x | Y | Y | Y | Y | Y |

Repository

This refers to the solution data stored in the BA Server, DI Server, or in a PDI database repository. This has nothing to do with data source support.

 **Note:** The DI Server has an integrated H2 solution database. Pentaho does not support using other solution databases -- including non-Pentaho H2 database instances -- at this time.

| | BA Server/Enterprise Console | Data Integration Server | Data Integration Engine | Data Integration Engine |
|--------------|------------------------------|-------------------------|-------------------------|-------------------------|
| DB2 | N | N/A | Y | Y |
| H2 Database | N | Y | Y | Y |
| Ingres | N | N/A | N | Y |
| MySQL 5.x | Y | N/A | Y | Y |
| Oracle | Y | N/A | Y | Y |
| Postgres 8.x | Y | N/A | Y | Y |
| SQL Server | N | N/A | Y | Y |

Data Sources

All databases that have a **JDBC version 3 driver with full ANSI SQL support** will work with the majority of Pentaho Business Analytics. Pentaho Data Integration includes JDBC drivers for most of its supported data sources. Pentaho Analysis has specific SQL dialect support for certain databases, but will work with others (possibly with poor performance) through its generic JDBC dialect.

| | BA Server/Enterprise Console | Data Integration Engine | Reporting Engine | Analysis Engine | Data Integration Engine | Design Studio | Report Designer | Data Integration Engine | Metadata Editor | Schema Workbench | Aggregation Designer |
|-------------------|------------------------------|-------------------------|------------------|-----------------|-------------------------|---------------|-----------------|-------------------------|-----------------|------------------|----------------------|
| Apache Derby | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| AS400 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Borland InterBase | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Cache | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| DB2 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| dBase III, IV, 5 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| EnterpriseDB | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Exasol | N | N | N | N | Y | N | N | Y | N | N | N |
| Excel | Y | Y | Y | N/A | Y | Y | N | Y | N | N/A | N/A |
| ExtenDB | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |

| | BA Server/ Enterprise Console | Data Integration Engine | Reporting Engine | Analysis Engine | Data Integration Engine | Design Studio | Report Designer | Data Integration Engine | Metadata Editor | Schema Workbench | Aggregation Designer |
|------------------------------|----------------------------------|-------------------------|------------------|-----------------|-------------------------|---------------|-----------------|-------------------------|-----------------|------------------|----------------------|
| Firebird SQL | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Generic (any JDBC) | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Gupta SQLBase | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| H2 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| HSQldb (formerly Hypersonic) | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Informix | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Ingres | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| LucidDB | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| MaxDB | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Microsoft Access | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| MySQL 5.x | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Netezza | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Oracle | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| OLAP (Analysis) | Y | Y | Y | N/A | N | Y | Y | N | N | N/A | N/A |
| Pentaho Metadata | Y | Y | Y | N/A | N | Y | Y | N | N/A | N/A | N/A |
| PlumTree | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Postgres | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| SAP | N | N | N | N | N | N | N | Y | N | N | N |
| SAP R/3 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| SQL Server 2005 | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| sqliteQ | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Sybase | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Teradata | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| Text files | Y | Y | Y | N/A | Y | Y | N | Y | N | N/A | N/A |
| UniVerse Database | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |
| XML | Y | Y | Y | N/A | Y | Y | N | Y | N | N/A | N/A |
| XML/A | Y | N | Y | N | N | Y | N | N | N | N | N |

Security

This refers to third-party authentication systems that can be integrated with the BA Server, DI Server, and Metadata Editor.

| | BA Server/ Enterprise Console | Data Integration Server | Metadata Editor |
|-----------------------------------|----------------------------------|-------------------------|-----------------|
| LDAP | Y | Y | Y |
| Active Directory | Y | Y | Y |
| RDBMS | Y | Y | Y |
| CAS | Y | N | Y |
| Integrated Windows Authentication | Y | N | Y |

Java Virtual Machines

This refers to the Java Runtime Environment (JRE) or Development Kit (JDK) required for running all Pentaho software. **Only the Sun/Oracle distribution is supported.** Ports and derivatives of the standard Oracle distribution (such as FreeBSD Diablo JDK) may work, but are not tested by Pentaho QA and therefore unsupported by Pentaho.

| | BA Server/Enterprise Console | Data Reporting Engine | Analysis Engine | Data Integration Engine | Design Studio | Report Designer | Data Integration | Metadata Editor | Schema Workbench | Aggregation Designer |
|-----------------|------------------------------|-----------------------|-----------------|-------------------------|---------------|-----------------|------------------|-----------------|------------------|----------------------|
| Sun v 1.6 (6.0) | Y | Y | Y | Y | Y | Y | Y | Y | Y | Y |

Web Browsers

A Web browser is required to use the Pentaho User Console (including Interactive Reporting, Analyzer, Dashboard Designer, Community Dashboard Framework, Data Source Wizard, JPivot, and ad hoc reporting) and Pentaho Enterprise Console. Report Designer requires a Web browser to preview reports exported to HTML format. If you use a browser other than one of those listed here, you will very likely encounter some kind of problem.

| | BA Server/ Enterprise Console | Report Designer |
|---------------------------|-------------------------------|-----------------|
| Internet Explorer 7, 8, 9 | Y | Y |
| Firefox 3.6, 9, 10 | Y | Y |
| Safari 5.x | Y | Y |
| Chrome | Y | Y |

Legend

Y = Supported

N = Not Supported

N/A = Not Applicable