Progress FUSE

FUSE™ Services Framework

Installation Guide

Version 2.2.x
April 2009

PROGRESS SOFTWARE

Installation Guide

Version 2.2.x

Publication date 17 Jul 2009
Copyright © 2001-2009 Progress Software Corporation and/or its subsidiaries or affiliates.

Legal Notices

Progress Software Corporation and/or its subsidiaries may have patents, patent applications, trademarks, copyrights, or other intellectual property rights covering subject matter in this publication. Except as expressly provided in any written license agreement from Progress Software Corporation, the furnishing of this publication does not give you any license to these patents, trademarks, copyrights, or other intellectual property. Any rights not expressly granted herein are reserved.

Progress, IONA, IONA Technologies, the IONA logo, Orbix, High Performance Integration, Artix;, FUSE, and Making Software Work Together are trademarks or registered trademarks of Progress Software Corporation and/or its subsidiaries in the US and other countries.

Java and J2EE are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and other countries. CORBA is a trademark or registered trademark of the Object Management Group, Inc. in the US and other countries. All other trademarks that appear herein are the property of their respective owners.

While the information in this publication is believed to be accurate Progress Software Corporation makes no warranty of any kind to this material including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. Progress Software Corporation shall not be liable for errors contained herein, or for incidental or consequential damages in connection with the furnishing, performance or use of this material.

All products or services mentioned in this manual are covered by the trademarks, service marks, or product names as designated by the companies who market those products.

No part of this publication may be reproduced, stored in a retrieval system or transmitted, in any form or by any means, photocopying, recording or otherwise, without prior written consent of Progress Software Corporation. No third-party intellectual property right liability is assumed with respect to the use of the information contained herein. Progress Software Corporation assumes no responsibility for errors or omissions contained in this publication. This publication and features described herein are subject to change without notice. Portions of this document may include Apache Foundation documentation, all rights reserved.

Table of Contents

1. Installation Prerequisites 9
Supported Platforms 10
Java Requirements 11
Other Suggested Prerequisites 12
Disk Space Requirements 14
Using FUSE Services Framework with Other Components 15
2. Installing FUSE Services Framework 17
Installer Files 18
Running the Installer 19
Installing in GUI Mode 20
Installing in Console Mode 22
Installing in Silent Mode 24
3. Installing from Source Code 27
Unpacking the Distribution 28
Building the Source 29
Distribution Files Built 30
4. Uninstalling FUSE Services Framework 31

List of Tables

1.1. Disk Space Requirements 14
1.2. Supported Deployment Environments 15
2.1. Installer Files 18
2.2. Command for Running the Installer in GUI Mode 20
2.3. Default Installation Directory 20
2.4. Command for Running the Installer in Silent Mode 24
2.5. Installer Properties 25

List of Examples

1.1. Windows Environment Script 12
1.2. UNIX and Linux Environment Script 13
2.1. Installer Properties File 26

Chapter 1. Installation Prerequisites

Before attempting to install and use FUSE Services Framework, make sure your system meets the minimum requirements.

Supported Platforms 10
Java Requirements 11
Other Suggested Prerequisites 12
Disk Space Requirements 14
Using FUSE Services Framework with Other Components 15

Supported Platforms

Progress tests and supports FUSE products on the platforms listed at http://fusesource.com/downloads/platforms-supported/.

Support for additional operating systems and versions is considered on a case-by-case basis.

Java Requirements

Java Runtime

To run applications developed with FUSE Services Framework, you must have JRE 1.5.0_11 or newer.

Important

Java 6 is supported from update 4 and onwards.

Java Development

To develop applications using FUSE Services Framework, you must have JDK 1.5.0_11 or newer.

Important

Java 6 is supported from update 4 and onwards.

Non-Sun Java distributions

Only JREs and JDKs distributed or OEMed from Sun Microsystems are supported. FUSE Services Framework is not guaranteed to run with gcj.

On Red Hat-derived Linux systems, gcj is the default Java distribution. In these cases, you must download and install a Sun JRE/JDK and set the `JAVA_HOME` environment variable. You can also integrate the Sun JRE/JDK into the `alternatives(1)` system. See the `alternatives(1)` man page for details.

JavaScript Environment

To develop and deploy JavaScript services, you need the Rhino JavaScript implementation. You can download Rhino from http://www.mozilla.org/rhino/download.html.

Other Suggested Prerequisites

These programs are not *required* to work with FUSE Services Framework. However, they are required to build the product from the source code. They are also used extensively by the sample applications.

Apache Ant

Building FUSE source and sample code requires Apache Ant 1.6.5 or later; you can download it from http://ant.apache.org/bindownload.cgi.

After unzipping the Apache Ant distribution, you must:

1. Set the `ANT_HOME` environment variable to the top-level directory where you unzipped Apache Ant.
2. Add Apache Ant's `bin` directory to your PATH.

Apache Maven

Apache Maven is a popular build management tool. FUSE source builds require Apache Maven 2.0.9 or later; you can download Apache Maven from http://maven.apache.org/download.html.

Once you have installed Apache Maven, you must:

1. Set the `M2_HOME` environment variable to point to the top-level directory that contains your Maven installation.
2. Add Maven's `bin` directory to the `PATH`.
3. Set the `MAVEN_OPTS` environment variable to `-Xmx512M` to give the Maven build more memory in which to run.

Environment Scripts

You can create scripts like the one shown here to make all settings for the required programs. You must adjust the paths in these examples to reflect your actual installed locations of Ant, Maven, and the JDK.

Example 1.1. Windows Environment Script

```
set JAVA_HOME=C:\Progra~1\Java\jdk1.5.0_11
set ANT_HOME=C:\Ant
set M2_HOME=C:\Maven
```

```
set PATH=%JAVA_HOME%\bin;%PATH%
set PATH=%ANT_HOME%\bin;%PATH%
set PATH=%M2_HOME%\bin;%PATH%
set MAVEN_OPTS=-Xmx512M
```

Example 1.2. UNIX and Linux Environment Script

```
export JAVA_HOME=/usr/lib/jvm/java-1.5.0-sun
export ANT_HOME=/opt/ant
export M2_HOME=/opt/maven
export PATH=$JAVA_HOME/bin:$PATH
export PATH=$ANT_HOME/bin:$PATH
export PATH=$M2_HOME/bin:$PATH
export MAVEN_OPTS=-Xmx512M
```

Disk Space Requirements

Table 1.1 on page 14 shows the amount of disk space you will need to install FUSE Services Framework.

Table 1.1. Disk Space Requirements

Installation Type	Windows	Linux
As installed by the Java installer	51 MB	52 MB
Source installation, as installed	23 MB	32 MB
Source installation, after building	229 MB [a]	260 MB [a]

[a] plus up to 600 MB placed in the Maven `$HOME/.m2` and `.maven` directories

Using FUSE Services Framework with Other Components

FUSE Services Framework is certified to support deployments into the following:

Table 1.2. Supported Deployment Environments

Product	Version
JBoss	4.0.4
Tomcat	5.5.17

Chapter 2. Installing FUSE Services Framework

The cross-platform FUSE Services Framework installer makes it easy to install the tools needed to build and deploy a SOA.

Installer Files 18
Running the Installer 19
Installing in GUI Mode 20
Installing in Console Mode 22
Installing in Silent Mode 24

Installer Files

Table 2.1 on page 18 lists the available installation files for FUSE Services Framework.

Table 2.1. Installer Files

File	Description
`fuse-services-framework-2.2.0.0-windows.exe`	Installer for Windows platforms.
`fuse-services-framework-2.2.0.0-unix.bin`	Installer for Linux, OS X, and all UNIX platforms.
`fuse-services-framework-2.2.0.0-src.zip`	Source code installation package for all platforms. If you prefer to build FUSE Services Framework from source, see "Installing from Source Code" on page 27.

Running the Installer

The installer is a Java application that can run in one of three modes:

- GUI on page 20
- Console on page 22
- Silent on page 24

Warning

Under certain conditions, the UNIX installer might throw an `InvocationTargetException` exception.

This is the result of a known bug in InstallAnywhere when `gcj` is the default Java version. The workaround is to install a Sun JVM and make sure its `java` executable is before any others on your path.

Installing in GUI Mode

Overview

By default, the installer runs as a Java GUI. In this mode, you have full control over what is installed on your local machine.

Running the installer

Use the following steps to install FUSE Services Framework in GUI mode:

1. For UNIX, log in as (or su to) the username that will own the FUSE Services Framework installation. The default installation path presumes your have root access, but you can specify any installation directory for which you have write rights.
2. Start the installer by entering the following command:

   Table 2.2. Command for Running the Installer in GUI Mode

Platform	Command
Windows	`fuse-services-framework-2.2.0.0-windows.exe`
UNIX	`sh fuse-services-framework-2.2.0.0-unix.bin`

3. Click **Next**.
4. Read and accept the **License Agreement**, then click **Next**.
5. Specify the top-level directory for your installation.

   Table 2.3. Default Installation Directory

Platform	Default Value
UNIX	`/opt/progress/fuse-services-framework-2.2.0.0`
Windows	`C:\progress\fuse-services-framework-2.2.0.0`

Tip

Click **Choose** to select a path by navigating to it.

6. Click **Next**.

7. If you are installing on Windows you will need to specify where the installer will create program icons.

Tip

If you want to install the icons for all users check the **Create Icons for All Users** box.

8. Click **Next**.
9. Choose a JDK for use by FUSE Services Framework.

   If the desired JDK is not on the list:

   - Click the **Search for Others** button to scan your computer for installed JREs.
   - Click the **Choose Another...** button to navigate to the location of your preferred JDK.

10. Click **Next**.
11. Review the installation summary.

    If you see something you need to correct, click the **Previous** button to go back through the installation steps.

    If the summary is correct, click **Install**.

12. Choose whether you want the installer to save the selected options in a properties file.

    The properties file is used to perform identical installations on other machines in a silent installation, as described in "Installing in Silent Mode" on page 24.

13. Click **Next**.
14. If you choose to save the installer properties, enter a path name for the properties file and click **Next**.
15. Click **Next**.
16. Click **Done** to complete the installation.

Installing in Console Mode

Overview

The installer's console mode is provided for situations where you want to have control over what is installed, but cannot launch a Java GUI. In console mode, you are presented with the same options as in GUI mode.

Note

Console mode is only for UNIX and Linux systems. Do not use the *-i console* option when installing on Windows.

Running the Installer

Use the following steps to install FUSE Services Framework using console mode:

1. Start the installer:

```
sh fuse-services-framework-2.2.0.0-unix.bin -i console
```

2. Press **Enter** a number of times to page through the license agreement.
3. Accept the license agreement by entering **Y**.

Note

Entering **N** exits the installer.

4. Press **Enter**.
5. Enter your the full path to a top-level directory to contain your installation.
6. Select a JDK from the list and press **Enter**.

Note

If you select `Choose a Java VM already installed on this machine`, you are asked to specified the full path to the Java VM executable file.

7. Review the installation summary.

8. If the summary is correct, press **Enter**.

Tip

You can type **`back`** to step backwards through the installer if the summary is not correct.

9. Choose whether to create a properties file.

   The properties file can be used to perform identical installations on other machines, as described in "Installing in Silent Mode" on page 24.

10. If you choose to save the installer properties, enter a path name for the properties file.

11. Press **Enter** to exit the installer.

Installing in Silent Mode

Overview

The installer's silent mode is intended for use in installing on remote machines. It is also useful for administrators to set up installations in which the person installing cannot change any installation options. You can customize how FUSE Services Framework is installed by providing an `installer.properties` file specifying the options you wish to install.

Running the Installer

To install FUSE Services Framework using the silent installation mode, do the following:

1. If you do not want a default installation, create an `installer.properties` file that specifies how you want FUSE Services Framework installed.

   You can create an installer.properties file in one of two ways:

   - Save one when running the installer in GUI or console mode.
   - Create a new one using a text editor. See Table 2.5 on page 25 for the possible entries.

2. Run the installer using the following command:

Table 2.4. Command for Running the Installer in Silent Mode

Platform	Command
Windows	**`fuse-services-framework-2.2.0.0-windows -i silent [-f installer.properties]`**
UNIX	**`sh fuse-services-framework-2.2.0.0-unix.bin -i silent [-f installer.properties]`**

The `-f` argument instructs the installer to load the specified properties file. (If you specify `-i silent` without the `-f` argument, the installer silently performs a default installation.)

Silent Installation Properties

Table 2.5 on page 25 shows the properties you can set and their possible values.

Note

When specifying Windows paths, escape the colon in drive letter specifications with a backslash, and double any backslash path separators. In your JDK_HOME entry, you can use the 8.3 version of space-containing directory names, but do not use space-containing path components in your USER_INSTALL_DIR entry. (Use **DIR /X** to determine the 8.3 version of file and directory names.)

Table 2.5. Installer Properties

Property	Values	Description
USER_INSTALL_DIR	The full path to the top-level directory where you want the product installed.	Specify a full absolute path, making sure no path component has a space in its name.
CHOSEN_INSTALL_FEATURE_LIST	A comma-separated list containing one or more of `CXF`, `Containers`, `Servlet`, and `Spring`.	Specifies a list of features to be installed. No spaces are allowed in the list; use only commas to separate feature entries.
SILENT_ACCEPT_LICENSE_AGREEMENT	`true` (default) or `false`	Specifies whether the installer accepts the license agreement without prompting.
JDK_HOME	The full absolute path to the JDK that FUSE Services Framework will use.	This is the same path that should be set in the `JAVA_HOME` environment variable.
INSTALLER_UI	`silent`, `gui` (default), or `console`	Specifies the mode in which the installer runs.
USER_INPUT_SAVE_PROPERTIES_YES_NO	`Yes` (default) or `No`	Specifies whether you want to save a properties file that describes the current run of the installer.
SET_PATH	This entry is not used by the FUSE Services Framework installer.	

Example Installer Properties File

Example 2.1 on page 26 shows a sample `installer.properties` file for a Windows system.

Example 2.1. Installer Properties File

```
❶ USER_INSTALL_DIR=C\:\\progress\\fuse-services-framework-2.2.0.0
❷ CHOSEN_INSTALL_FEATURE_LIST=CXF,Containers,Spring
❸ SILENT_ACCEPT_LICENSE_AGREEMENT=true
❹ JDK_HOME=C\:\\Progra~1\\Java\\jdk1.5.0_11
❺ INSTALLER_UI=silent
❻ USER_INPUT_SAVE_PROPERTIES_YES_NO=No
```

The properties file shown in Example 2.1 on page 26 tells the installer to do the following:

❶ Install FUSE Services Framework into `C\:\\progress\\fuse-services-framework-2.2.x`.

❷ Install all FUSE Services Framework components.

❸ Accept the license agreement without prompting.

❹ Use the specified JDK.

❺ Run the installer silently.

❻ Do not save an `installer.properties` file.

Chapter 3. Installing from Source Code

The FUSE Services Framework source distribution includes the source code and tools for building a number of the components included in FUSE Services Framework. Once built, you can use them to create an installation of FUSE Services Framework.

Unpacking the Distribution 28
Building the Source 29
Distribution Files Built 30

Before installing product from source code, do the following:

1. Read this chapter to make sure you understand the build process.
2. Make sure your system has the required tools for building from source.
3. Make sure your system meets the minimum requirements for using FUSE.

Unpacking the Distribution

The source distribution is packaged as a `.zip` file that must be unpacked before you can build the FUSE Services Framework installation. Unpack the distribution into a directory to which you have full access.

Warning

Do not unpack the archive file into a folder that has spaces in its path name. For example, do not unpack into `C:\Documents and Settings\Greco Roman\Desktop\fusesrc`.

Building the Source

Build the FUSE Services Framework distribution by doing the following:

1. Change to the folder into which you unpacked the source distribution.
2. Run the following command:

```
mvn -Pfastinstall
```

Note

You can run the with all unit tests the following command.

```
mvn -Peverything install
```

Building with tests enabled takes much longer.

3. Change to the `distribution` folder of the unpacked source
4. Run the following command:

```
mvn
```

Distribution Files Built

When the build runs successfully, FUSE Services Framework distribution `.zip` and `.tar.gz` files are found in the `cxf/distribution/target` folder of the source distribution directory.

To install FUSE Services Framework from the a newly built distribution file, unzip its contents into the directory of your choice.

Chapter 4. Uninstalling FUSE Services Framework

This chapter describes how to uninstall FUSE Services Framework.

Uninstalling On Windows Systems

To uninstall FUSE Services Framework on a Windows system, do the following:

1. From the Windows **Start** menu, select **(All) Programs** → **Progress** → **FUSE Services Framework 2.2.x** → **Uninstall FUSE Services Framework 2.2.x**.
2. Click **Uninstall**.

As an alternative, you can run the following from a command prompt:

```
InstallDir\uninstall\uninstall-fuse-services-framework.exe
```

Uninstalling on UNIX Systems

To uninstall FUSE Services Framework on Linux and UNIX systems, run the following script:

```
InstallDir/uninstall/uninstall-fuse-services-framework
```

Important

Remember that after a silent installation, the next uninstallation is also run silently.