openCRX Server Installation

Version 2.1.0



www.opencrx.org

License

The contents of this file are subject to a BSD license (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at http://www.opencrx.org/license.htm

Copyright 2008 © CRIXP Corp. All rights reserved.

Table of Contents

About	this Book	3
1.1	Who this book is for	3
1.2	What do you need to understand this book	3
1.3	Tips, Warnings, etc	3
Preree	guisites	4
2.1	JDK 5.0	4
2.2	openMDX Tomcat LWC Installer	5
2.3	openCRX Server Installer	5
2.4	Hardware	5
Instal	lling openCRX Server on Windows	6
3.1	Apache Tomcat / LWC	6
3.2	openCRX	12
Instal	lling openCRX Server on Linux	
4.1	Apache Tomcat / I WC	
4.2	openCRX	
Runni	ng openCRX Server	26
5 1	Starting openCDV Server	20 26
5.1		20
5.2	Connect and Login	26
5.3	Stopping openCRX Server	26
Next S	Steps	27
	About 1.1 1.2 1.3 Prere 2.1 2.2 2.3 2.4 Instal 3.1 3.2 Instal 4.1 4.2 Runni 5.1 5.2 5.3 Next S	About this Book.1.1Who this book is for.1.2What do you need to understand this book.1.3Tips, Warnings, etc.Prerequisites.2.1JDK 5.0.2.2openMDX Tomcat LWC Installer.2.3openCRX Server Installer.2.4Hardware.Installing openCRX Server on Windows.3.1Apache Tomcat / LWC.3.2openCRX Server on Linux.4.1Apache Tomcat / LWC.4.2openCRX5.1Starting openCRX Server.5.2Connect and Login.5.3Stopping openCRX Server.

List of Figures

List of Listings

1 About this Book

This book describes how to **install an openCRX Server** with the BitRock installer **on Windows or Linux** platforms. Please note that this is a guide to set up a **runtime environment** suitable for evaluation and testing purposes. It is not recommended to use this configuration for a production site.

openCRX is the leading enterprise-class open source CRM suite. openCRX is based on openMDX, an open source MDA framework based on the OMG's model driven architecture (MDA) standards. This guarantees total openness, standards compliance, a state-of-the-art component-based architecture, and virtually unlimited scalability.

1.1 Who this book is for

The intended audience are openCRX administrators and advanced users interested in evaluating openCRX.

1.2 What do you need to understand this book

This book describes how to install openCRX with the BitRock installer, which takes care of all the tricky configuration issues for you. The prerequisites are minimal (JDK) and once they are met you should have openCRX up and running in less than 5 minutes.

1.3 Tips, Warnings, etc.

We make use the following pictograms:



Information provided as a "Tip" might be helpful for various reasons: time savings, risk reduction, etc. - it goes without saying that we advise to follow our guides meticulously

> **meticulous** \muh-TIK-yuh-luhs\, *adjective*: Extremely or excessively careful about details.



You should carefully read information marked with "Important". Ignoring such information is typically not a good idea.



Warnings should not be ignored (risk of data loss, etc.)

2 Prerequisites

2.1 JDK 5.0

Install either the Sun Java JDK 5.0 or the BEA JRockit JDK 5.0 appropriate for your platform. The JDKs are available from the following sites:

<u>Sun JDK 5.0:</u> http://java.sun.com/javase/downloads/index_jdk5.jsp

<u>Oracle/BEA JRockit JDK 5.0:</u> http://www.oracle.com/technology/software/products/jrockit/index.html



You really need Java 5, i.e. neither Java 4 nor Java 6 will work.



Unless you are a Sun Java VM expert **we recommend Oracle/BEA JRockit for production use**. The reason is the following one:

If you deploy openCRX on Sun's JVM you might run into a problem that is mind-boggling (but specific to the Sun JVM). It's the dreaded

PermGen OutOfMemoryError

Lots of people have been struggling with this error (which is by the way not related to openCRX – any application could trigger it) and as of today we have not come across a solution other than to avoid Sun's JVM (JVMs by Oracle/BEA and IBM are – by construction – not prone to this error). Do a Google search if you want to convince yourself or drop us a line if you have a solution. But be aware that increasing the memory allocated for the permanent generation is no solution – it will only postpone the problem:

- http://my.opera.com/karmazilla/blog/2007/03/13/good-riddance-permgen-outofmemoryerror
- http://my.opera.com/karmazilla/blog/2007/03/15/permgen-strikes-back
- http://crashingdaily.wordpress.com/2007/02/04/crashing-tomcat/



It is not sufficient to have a Java Runtime Environment (JRE) only. The full-blown **JDK** is required to run openCRX.



Don't forget to set the **environment variable** JAVA_HOME

2.2 openMDX Tomcat LWC Installer

Download the openMDX Tomcat LWC Installer appropriate for your platform from Sourceforge: http://www.openmdx.org/downloads.htm

Installer for Windows: openmdxTomcatLwc-2.1.0-windows-installer.exe

Installer for Linux: openmdxTomcatLwc-2.1.0-linux-installer.bin

The openMDX Tomcat LWC Installer will install Apache Tomcat v6.0.14 including the openMDX Lightweight Container (LWC) on your system.

2.3 openCRX Server Installer

Download the openCRX Server Installer appropriate for your platform from Sourceforge: http://www.opencrx.org/downloads.htm

Installer for Windows: opencrxServer-2.1.0-windows-installer.exe

Installer for Linux:

opencrxServer-2.1.0-linux-installer.bin

The openCRX Server Installer will install the openCRX EARs, an openCRX database (HSDQLDB), and various configuration files on your system.

2.4 Hardware

We recommend a decent CPU and at least 1GB RAM. More detailed information about the requirements of openCRX are available from http://www.opencrx.org/faq.htm#hardware

3 Installing openCRX Server on Windows

3.1 Apache Tomcat / LWC

- 1. Launch the Installer openmdxTomcatLwc-2.1.0-windows-installer.exe
- 2. Click [Next] on the following screen:



3. Accept the BSD License Agreement and click [Next] again:

📑 Setup		X
License Agreement	operno	dx
Please read the following Lice continuing with the installation	ense Agreement. You must accept the terms of this agreement befor n.	re
This software is publ as listed below.	lished under the BSD license	
Copyright (c) 2004-2008, OMEX AG, Switzerland All rights reserved.		
Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:		
Do you accept this license?	 I accept the agreement I do not accept the agreement 	
DICHOCK INSIGNED	< Back Next > Cancel	

4. Choose an **installation directory** (it will be created automatically if it does not exist yet). Then click [Next] to continue:

💰 Setup	_ 🗆 🛛
Installation Directory	• opemdx
Please specify the directory where openMDX Tomcat+LWC will be installed.	
Installation Directory P:\openmdxTomcatLwc-2.1.0	
BitRock Installer	Cancel

5. Please note the information on the following screen. It is assumed that you have installed JDK 1.5 (also called JDK 5.0) appropriate for your platform (see Prerequisites). Click [Next] to continue:

📑 Setup 🗧	. 🗆 🛛
	<mark>enıd</mark> x
Installation instructions	
This installer creates a Tomcat 6 instance extended by the op- Lightweight EJB Container. The installer does NOT include the 1.5 binaries. Make sure you have these packages installed before continuing.	anMDX JDK pre
BitRock Installer	incel

6. Select the home directory of your JDK 1.5 installation - for example
 D:\Java\jrockit1.5.0 - and then click [Next] to continue:

📑 Setup				
JDK 1.5 home direct	ory		- P _	openıdx
Select home directory of an existing JDK 1.5, e.g. C:\pgm\Java\jdk1.5.0 on Windows or /usr/lib/jvm/jdk1.5.0 on Linux platforms.				
JDK 1.5 home directory	D:\Java\jrockit1.5.0		6	
BitRock Installer				
		< Back	Next >	Cancel

7. Enter the port number of the **Tomcat HTTP connector**. You can choose any port available on your system. The default is **8080**. Click [Next] to continue:

📑 Setup		
Tomcat HTTP po	rt	spendx opendx
Please enter the po	rt number for the Tomcat HTTP connector.	
Tomcat HTTP port	8080]
BitRock Installer		
	< Back	Next > Cancel

8. Similarly, enter the port number of the **Tomat HTTPS Connector**. The default is **8443**. Click [Next] to continue:

📑 Setup	
Tomcat HTTPS port	opemdx
Please enter the port number for the Tomcat HTTPS connector.	
Tomcat HTTPS port 8443	
BitRock Installer	
< Back Next >	Cancel

9. Next, enter the **Tomcat command port** number. The default is **8005**. Click [Next] to continue:

📑 Setup	\square
Tomcat server port	soperndx and the second
Please enter the port number of the Tomcat server.	
Tomcat server port 8005	
BitRock Installer	
< Back Ne	xt > Cancel

10. Enter the port number of the **Tomcat AJP connector**. The default is **8009**. Click [Next] to continue:

🕞 Setup	
Tomcat AJP port	operndx •
Please enter the port number of the Tomcat AJP connector.	
Tomcat AJP port 8009	
BitRock Installer	
< Back N	ext > Cancel

11. Finally, click [Next] to start the installation:

📑 Setup	
Ready to Install	opemdx 🕹
Setup is now ready to begin installing openMD	X Tomcat+LWC on your computer.
BitBock Installer	
	< Back Next > Cancel

12. Once the installation is complete, verify the result of the post installation script and click [Ok]:



13. Click [Finish] on the last screen to leave the installer:

📑 Setup	
	Completing the openMDX Tomcat+LWC Setup Wizard Setup has finished installing openMDX Tomcat+LWC on your computer. ✓ View Readme File
	< Back Finish Cancel

14. On your desktop, you should see the following new shortcuts created by the installer:



3.2 openCRX

1. Launch the Installer opencrxServer-2.1.0-windows-installer.exe

2. Click [Next] on the following screen:



3. Accept the BSD License Agreement and click [Next] again:

📑 Setup 📃 🗖	X
License Agreement	rx
Please read the following License Agreement. You must accept the terms of this agreement befor continuing with the installation.	e
This software is published under the BSD license as listed below.	
Copyright (c) 2004-2008, CRIXP Corp., Switzerland All rights reserved.	
Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:	~
Do you accept this license? I accept the agreement I do not accept the agreement I do not accept the agreement	
BitRock Installer < Back	

 On the following screen, navigate to the Tomcat installation directory – for example P:\openmdxTomcatLwc-2.1.0 – and then click [Next] to continue:

📑 Setup		
Tomcat+LWC director	y	Copencrx
openCRX is added to an ex	isting Tomcat+LWC installation.	
Tomcat+LWC directory	?:\openmdxTomcatLwc-2.1.0	<u> </u>
BitRock Installer		
	< Back	Next > Cancel

5. Please note the information on the following screen and then click [Next] to continue:

📑 Setup	
IMPORTANT	Copencrx
Installation instructions	
This installer adds openCRX to an e installation. The installation come database. The installer does NOT in sure you have this package installe	xisting openMDX Tomcat+LWC s with a preconfigured HSQLDB clude openMDX Tomcat+LWC. Make d before continuing.
BitRock Installer	< Back Next > Cancel

6. Enter the port number of the **HSQLDB service**. You can choose any port available on your system. The default is **9001**. Click [Next] to continue:

📑 Setup	🛛
HSQLDB port	Copencrx
Please enter the port number for the HSQLDB service.	
HSQLDB port 9001	
BitRock Installer	
< Back	Next > Cancel

7. Finally, click [Next] to start the installation:

📑 Setup	
Ready to Install	Copencrx
Setup is now ready to begin installing openCRX Server on your comput	er.
BitRock Installer	Next > Cancel

8. Once the installation is complete, click [Finish] on the last screen:

😼 Setup	
	Completing the openCRX Server Setup Wizard Setup has finished installing openCRX Server on your computer.
	< Back Finish Cancel

9. Finally, please carefully read the README, in particular information about **valid URLs**, preconfigured **users** and **passwords**:



10. On your desktop, you should see the following new shortcut created by the installer:



4 Installing openCRX Server on Linux



There is no need to install openCRX as root. We created a user **crx** and the whole installation procedure is done as user **crx**.

4.1 Apache Tomcat / LWC

- 1. Launch the Installer openmdxTomcatLwc-2.1.0-linux-installer.bin
- 2. Click [Forward] on the following screen:



3. Accept the BSD License Agreement and click [Forward] again:

	Setup	
License Agreement	<u>م</u>	open ıdx
Please read the following Lic agreement before continuing This software is pu as listed below.	ense Agreement. You must accept t g with the installation. blished under the BSD li	the terms of this .cense
Copyright (c) 2004- All rights reserved	2008, OMEX AG, Switzerla	and 🚽
Do you accept this license?	 I accept the agreement I do not accept the agreement 	
BitRock Installer ———	🗢 <u>B</u> ack 🖨 🖨 Back	X Cancel

4. Choose an **installation directory** (it will be created automatically if it does not exist yet). Then click [Forward] to continue:

3000	Setup	
Installation Direct	ory	operndx 🕹
Please specify the dir	ectory where openMDX Tomcat+	LWC will be installed.
Installation Directory	/home/crx/openmdxTomcatLwc-	2.1.0
BitRock Installer ——		
	🗢 <u>B</u> ack	Eorward

5. Please note the information on the following screen. It is assumed that you have installed JDK 1.5 (also called JDK 5.0) appropriate for your platform (see Prerequisites). Click [Forward] to continue:

	Setup	_ 🗆 🗙
IMPORTANT		soperndx operndx
Installation instruction This installer creates Lightweight EJB Conta binaries. Make sure y	s a Tomcat 6 instance extended by the iner. The installer does NOT include t ou have these packages installed be	openMDX he JDK 1.5 fore continuing.
BitRock Installer ——	🗢 <u>B</u> ack 🖨 Eor	ward

6. Select the home directory of your JDK 1.5 installation - for example **/opt/jrockit-1.5.0_12** - and then click [Forward] to continue:

×≕ S	ietup 📃 🗆		
JDK 1.5 home directory	opem 🕹	dx	
Select home directory of an existin Windows or /usr/lib/jvm/jdk1.5.0 on	Select home directory of an existing JDK 1.5, e.g. C:\pgm\Java\jdk1.5.0 on Windows or /usr/lib/jvm/jdk1.5.0 on Linux platforms.		
JDK 1.5 home directory /opt/jrocki	it-1.5.0_12	7	
BitRock Installer ———	⊕ Eorward ★ Cance ▲	!	

7. Enter the port number of the **Tomcat HTTP connector**. You can choose any port available on your system. The default is **8080**. Click [Forward] to continue:

200	Setup	
Tomcat HTTP port	•	🦆 opemdx
Please enter the port number fo	or the Tomcat HTTP connector.	
Tomcat HTTP port 8080		
BitRock Installer —		
		d X Cancel

8. Similarly, enter the port number of the **Tomat HTTPS Connector**. The default is **8443**. Click [Forward] to continue:

9000 C	Setup	
Tomcat HTTPS port	•	Se opernd x
Please enter the port number for	r the Tomcat HTTPS connector.	
Tomcat HTTPS port 8443		
BitRock Installer		
	⊕ Eorward ↓ ☐	X <u>C</u> ancel

9. Next, enter the **Tomcat command port** number. The default is **8005**. Click [Forward] to continue:

x==	Setup	
Tomcat server port		🍫 opemdx
Please enter the port n	umber of the Tomcat server.	
Tomcat server port 80	05	
BitRock Installer ———	A Back	Forward Cancel

10. Enter the port number of the **Tomcat AJP connector**. The default is **8009**. Click [Forward] to continue:

	🖛 Setup 💶 🗙		
	Tomcat AJP port		
	Please enter the port number of the Tomcat AJP connector.		
	Tomcat AJP port 8009		
	BitRock Installer		
1.	Finally, click [Forward] to start the installation:		
	🗯 Setup 💶 🗙		
	Ready to Install opendx		

Setup is now ready to begin installing openMDX Tomcat+LWC on your computer.

- BitRock Installer BitRock Installer Back Eorward Scancel 12. Once the installation is complete, you might see a window containing the
- 12. Once the installation is complete, you might see a window containing the result of the post installation script. Click [Ok] to close the window

13. <u>Click [Finish] on the last screen to leave the installer:</u>



14. On your desktop, you should see the following new shortcuts created by the installer:



4.2 openCRX

- 1. Launch the Installer opencrxServer-2.1.0-linux-installer.bin
- 2. Click [Forward] on the following screen:



3. Accept the BSD License Agreement and click [Forward] again:

	وسدده	
License Agreement		Copencrx
Please read the following Lic agreement before continuin This software is pu	ense Agreement. You mus g with the installation. blished under the	st accept the terms of this
as listed below.		=
Copyright (c) 2004- All rights reserved	2008, CRIXP Corp. I.	, Switzerland
Redistribution and with or without modification are n	use in source and permitted provided	binary forms,
Collouing condition		
Do you accept this license?	I accept the agreement	nt
bo you decept and neense.	 I do not accept the ag 	reement
BitRock Installer		
	🔷 <u>B</u> ack 🖨	Eorward X Cancel

 On the following screen, navigate to the Tomcat installation directory – for example /home/crx/openmdxTomcatLwc-2.1.0 – and then click [Forward] to continue:

🖛 Setup	
Tomcat+LWC directory	Copencrx
openCRX is added to an existing Tomcat+LWC installation	1.
Tomcat+LWC directory //home/crx/openmdxTomcatLwc-	2.1.0
BitRock Installer	
🔶 <u>B</u> ack	orward X Cancel

5. Please note the information on the following screen and then click [Forward] to continue:

—	Setup	
IMPORTANT		Copencrx
Installation instructions		
This installer adds openCRX to an installation. The installation come The installer does NOT include o this package installed before co	n existing openMDX Tomcat s with a preconfigured HSC penMDX Tomcat+LWC. Mak ntinuing.	:+LWC QLDB database. e sure you have
BitRock Installer ————	⊕ Eorw	vard

6. Enter the port number of the **HSQLDB service**. You can choose any port <u>available on your system</u>. The default is **9001**. Click [Forward] to continue:

E	Setup	
HSQLDB port		Copencrx
Please enter the port number fo	or the HSQLDB service.	
HSQLDB port 9001		
BitRock Installer		
	⊕ Eo	rward X Cancel

7. Finally, click [Forward] to start the installation:

(and	Setup	
Ready to Install		Copencrx
Setup is now ready to begin ins	talling openCRX Server on	your computer.
BitRock Installer		
	🗢 <u>B</u> ack	ward X Cancel

8. Once the installation is complete, click [Finish] on the last screen:



9. Finally, please carefully read the README, in particular information about **valid URLs**, preconfigured **users** and **passwords**:

README	
login using a browser. Valid URLs are:	
* openCRX/Core: http://localhost: <tomcat_port>/opencrx-core-CRX * openCRX/Store: http://localhost:<tomcat_port>/opencrx-store-CRX/ * openCRX/Wiki: http://localhost:<tomcat_port>/opencrx-wiki-CRX/</tomcat_port></tomcat_port></tomcat_port>	Store =
The following accounts are preconfigured:	
* guest * admin-Standard	
* admin-Root The password for all three accounts is 'opencrx'.	•
<i>щ</i> <u>о</u> к	

10. On your desktop, you should see the following new shortcut created by the installer:



5 Running openCRX Server

The installation process created 5 shortcuts on your desktop:



Launch Browser and connect to Tomcat Stop Tomcat to stop the openCRX Server Most likely you won't need this shortcut

Start Tomcat to start the openCRX Server

Most likely you won't need this shortcut Nevertheless, with this shortcut you could launch scripts named 001S.bat/sh, 002S.bat/sh, ... located in the Tomcat directory ./bin without actually starting Tomcat – currently, only HSDLDB installs a start script.

Launch Management Console of HSDQLDB

5.1 Starting openCRX Server

Double-click the shortcut **Start Tomcat+LWC**.

5.2 Connect and Login

Double-click the shortcut **Login Tomcat+LWC**. This will launch your default browser and take you to the Tomcat home page. In the lower left corner you will see a box labelled openCRX CRM:

openCRX CRM	
openCRX Core openCRX Wiki	
openCRX Store	

Click on **openCRX Core** to load the openCRX login page. Enter a valid username (e.g. guest) and the corresponding password (e.g. opencrx) and then click [Login]. Initialization takes place during the first login after (re)starting Tomcat, so please be patient. Subsequent logins will be very fast.

5.3 Stopping openCRX Server

Double-click the shortcut **Stop Tomcat+LWC**.

6 Next Steps

Now that you have successfully installed openCRX you might want to have a look at some of the additional documentation published at http://www.opencrx.org/documents.htm.